
iradinaGUI Documentation

Release 1.0.0

CEA DEN/DANS/DM2S/STMF/LGLS

Oct 06, 2020

CONTENTS

1	User's manual	3
1.1	Iradina GUI main widget	4
1.2	Iradina tree view widget	5
1.3	Log Run Code widget	7
1.4	Explore Dir widget	9
1.5	Plot widget	13
1.6	Plot widget usage	16
1.7	Tips	20
2	Programmer's guide	25
2.1	Prerequisites	26
2.2	All-in-one installation	26
2.3	All-in-one installation Linux	26
2.4	All-in-one installation Windows7-10	27
2.5	Development installations	28
2.6	IradinaGUI configuration	30
2.7	Usage of iradinaGUI	31
2.8	Iradina code compilation	32
2.9	Documentation	34
3	Frequently Asked Questions	37
3.1	Add an Item in this FAQ	38
3.2	FAQ	38
4	Code documentation	39
4.1	Code documentation	40
5	Release Notes	75
5.1	Release notes	75
	Python Module Index	77
	Index	79



Warning:

1. Find a *pdf* version of this documentation [here](#)¹.
2. Find *Iradina code* manual [here](#)².

The iradinaGUI code is a [GUI](#)³ (Graphical User Interface) used to perform operations with [Iradina code](#).

This GUI code is a set of [Python3](#)⁴ scripts files.

¹ iradinaGUI/doc/build/latex/iradinaGUI.pdf

² iradinaGUI/doc/src/iradinaDocuments/20140804_iradina_manual.pdf

³ https://en.wikipedia.org/wiki/Graphical_user_interface


⁴ <https://docs.python.org/3.5>

USER'S MANUAL

1.1 Iradina GUI main widget

From this main widget named *Iradina GUI* users can:

1. Prepare Iradina code data.
2. Run Iradina code.
3. Plot curves from result files of Iradina code runs.



1.1.1 Main widget toolbar




This toolbar contains icons related to actions, from left to right:

1. New Iradina data. Create iradina case from scratch
2. Load Iradina data. Load case from previously saved case in a file Xml.
3. Save Iradina data. Save current iradina case in a file Xml.
4. Launch Iradina calculus. Launch Iradina code on current iradina case.
5. Refresh IradinaObjects tree view.
6. Clear Iradina data model, remove Iradina data tree (in IradinaObject widget).
7. Iradina GUI help. Display this current documentation in a browser (html mode).
8. Iradina code help. Display Iradina code manual in a browser (pdf mode).

1.2 Iradina tree view widget

From this tree view widget named *IradinaObjects* users can:

1. Prepare Iradina code data.



Name	Value
Iradina	
Controls	
Analysis	
dataInformations	
caselradina	
IonBeam	
ion	
symbolElement	Xe
isotopeNumero	133
atomicNumber	54
atomicWeight	1.31290e+02
ionE0	3.90000e+02
ion_angle_xy	0
ion_distribution	((1) Centered
Target	
straggling_model	((3) Chu + Yang correctio...
Materials	
0	
name	UO2
IsVacuum	False
TargetConcentration	1.00000e+00
Density	1.09700e+01
IonSurfEnergy	0.00000e+00
Components	
0	
Component	
symbolEle...	U
isotopeNu...	238
atomicNu...	92
atomicWe...	2.38000e+02
Density	1.90000e+01
ElementConc	1.00000e+00
ElementDisp...	4.00000e+01
ElementLatt...	4.00000e+00
ElementSurf...	4.00000e+00

1.2.1 Modify tree view widget items values


There are some values as leaves of tree. Names and tooltips are *almost* as Iradina code naming usage.

1. **Simple scalar values.** User can modify value on *mouse-left-double-click*, selecting tree item nodes **hovering column value**.
2. **Other specific values.** User can modify value on *mouse-right-click*, to get a contextual menu for modification, selecting tree item nodes **hovering columns name and value**.

1.2.2 Tree view widget menus


There are some menus, as *contextual menu* on *mouse-right-click* when selected tree item nodes. Some menu are generic, and other are specific to node, as contextual actions. This is a **NOT exhaustive** list of menus:

Expand/collapse menu



This menu contains some actions to expand or collapse all or selected part of data tree. To activate this menu users have to *mouse-right-click* on **head of arrow** of tree item nodes (at **left** of item icon).

Delete/Insert menu




This menu contains some actions to insert, delete and reset all or selected part of data tree. To activate this menu users have to *mouse-right-click* on 'name' of tree item nodes (at right of item icon). The concerned items are usually not leaves (are items without a value).

1.3 Log Run Code widget

This widget displays log trace of Iradina code execution.

Iradina code is executed when users activate *Launch Iradina calculus* button in *Main widget toolbar* (page 4).




The screenshot shows a window titled "Log Run Code" with a tab labeled "Explore Dir". The main area displays a terminal window with the following content:

```
set -x
studyDir=/data/tmplgls/wambeke/IRADINAGUI_WORKDIR/test_U02
iradinaExe=/data/tmplgls/wambeke/iradinaGUI/iradinaCode/iradina_linux64.exe
cd $studyDir
tree
ls -alt
( $iradinaExe -p 9 -data ../data -c ./Configuration.in | tee ./iradina.log )&
# to see iradina progress
# tail -f /data/tmplgls/wambeke/IRADINAGUI_WORKDIR/test_U02/iradina.log

+ studyDir=/data/tmplgls/wambeke/IRADINAGUI_WORKDIR/test_U02
+ iradinaExe=/data/tmplgls/wambeke/iradinaGUI/iradinaCode/iradina_linux64.exe
+ cd /data/tmplgls/wambeke/IRADINAGUI_WORKDIR/test_U02
+ tree
.
├── Composition.in
├── Configuration.in
├── iradinaGui.xml
├── iradina.log
├── launchIRADINA.bat
├── launchIRADINA.sh
├── Materials.in
├── output
│   ├── ira.disp.sum
│   ├── ira.disp.z8.m16.000.mat0.elem1
│   ├── ira.disp.z92.m238.000.mat0.elem0
│   ├── ira.information
│   ├── ira.int.sum
│   ├── ira.int.z8.m16.000.mat0.elem1
│   └── ira.int.z92.m238.000.mat0.elem0
```

The status bar at the bottom of the window shows "Ready".

1.3.1 Log Run Code widget menu



This menu contains some actions to display, but **also** edit all or selected part of current log trace, considering log trace as an ascii file. To activate this menu users have to *mouse-right-click* **somewhere in** Log Run Code widget.


Note: Using *Open* and *Save* actions in this menu, users can use this widget as an elementary text file viewer/editor.

1.4 Explore Dir widget

This widget displays the contents of user iradinaGUI working directory. This directory is usually referenced as *IRADINAGUI_WORKDIR*.

Its usage is like a **simple** file explorer.

Note: Theses result files of Iradina code are located in sub-directories named *output*.




There are three main widgets (from left to right):

1. Directories names widget
2. Files names widget
3. File contents widget

Note: The lower *selected files* widget is for future improvements, no usage *yet*.


There are some contextual menus to explore directories, and to display input/output text files.

1.4.1 Directories names widget menu



This menu contains some elementary actions to navigate in **all** disk directories.


1.4.2 Files names widget menu



This menu contains some actions to apply on selected file.

Note: An useful action is the lower **matplotlib plot**, to plot curves from result files of Iradina code as post-treatment.

1.4.3 Files contents widget menu



This menu contains some elementary actions to apply on displayed file. The files are *syntax highlighted* if possible, using [highlight⁵](http://www.andre-simon.de/doku/highlight/en/highlight.php) tool, only on Linux distributions for now.

Warning: The lower *highlight theme* action is displayed only for Linux distribution.

⁵ <http://www.andre-simon.de/doku/highlight/en/highlight.php>


1.5 Plot widget

This widget is to explore, modify and make plots from data. It appears when users activate **matplotlib plot** in *Files names widget menu* (page 11).

It uses some important Python packages:

1. **PANDAS**⁶ (Python Data Analysis Library) to read and store data in memory.
2. **MATPLOTLIB**⁷ (Python 2D plotting library) to plot curves.

Warning: Data are read from **CSV**⁸ formatted files. Note that result files of Iradina code use whitespace/tabulation for separator character, *not comma*, for readability.



There are four main widgets (from up to down, left to right):


1. Plots toolbar widget
2. Infos tab widget
3. Contents tab widget
4. Plots tab widget

⁶ <https://pandas.pydata.org>

⁷ <https://matplotlib.org>

⁸ https://en.wikipedia.org/wiki/Comma-separated_values

1.5.1 Plot toolbar widget



This menu contains some buttons, as actions, which are, from left to right:

1. Read a new data set from file, [CSV](#)⁹ formatted.
2. Plot curve $y=f(x)$. 2 columns (x,y) selected.
3. Plot 2 curves $(y_1,y_2)=f(x)$, two distinct Y-axis. 3 columns (x,y1,y2) selected.
4. Plot n curves $y_1, \dots, y_n=f(x)$, one Y-axis, (n+1) columns (x,y1, ... yn) selected.
5. Plot n *distinct* curves $y_1, \dots, y_n=f(x)$, (n+1) columns (x,y1, ... yn) selected.
6. Plot histogram, one columns selected, (automatic number of intervals).
7. Execute [PANDAS](#)¹⁰ expressions, modification **on the fly** of *Contents tab widget*.
8. Initialize data **ellipse** in *Contents tab widget* (as a *newbie example*), plot the ellipse.

With this toolbar, user may process:

1. Select one, or more columns in *Contents tab widget*, then call plot of curve(s) using plot buttons of this plot toolbar. A MATPLOTLIB plot is displayed in *Plots tab widget*. See [Example of user plot](#) (page 18).
2. Create, remove, calculate new(s) columns of data in *Contents tab widget*. See [Example of user PANDAS expression](#) (page 16).
3. Filter, sort etc. lines of data in *Contents tab widget*, that means also get (and trace) a subset of *Contents tab widget*.

⁹ https://en.wikipedia.org/wiki/Comma-separated_values

¹⁰ <https://pandas.pydata.org>

1.5.2 Infos tab widget

Infos	Contents	Plots
0		
nbCols	3	
nbRows	1000	
periods	1000	
suptitle	from getExampleDataFrameEllipse	
title	ellipse	
xtitle	x	
ytitle	y=f(x)	


This widget contains some contextual informations from CSV data file, if they are present.

1.5.3 Contents tab widget

Infos		Contents		Plots	
		teta	X	Y	
0	0.0	1.0	0.0		
1	0.03144737...	0.99860511...	0.03141386...		
2	0.06289474...	0.99622453...	0.06274004...		
3	0.09434212...	0.99286239...	0.09394763...		
4	0.12578949...	0.98852379...	0.12500592...		
5	0.15723686...	0.98321479...	0.15588440...		
6	0.18868424...	0.97694240...	0.18655277...		
7	0.22013161...	0.96971459...	0.21698103...		
8	0.25157899...	0.96154023...	0.24713943...		


This widget displays current data, allowing some *elementary* modifications (see your appropriate spreadsheet for more functionalities (Excel, or else)).

1.5.4 Plots tab widget



This widget displays current plot, as an instance of [matplotlib](https://matplotlib.org)¹¹ figure.

1.5.5 Interactive navigation toolbar matplotlib




Using this standard toolbar of [matplotlib](https://matplotlib.org)¹², user may customize current plot.

For more informations, users should refer to the description of [navigation toolbar MATPLOTLIB](http://matplotlib.org/users/navigation_toolbar.html)¹³.

1.6 Plot widget usage

1.6.1 Example of user PANDAS expression

User may modify data of [Contents tab widget](#) (page 15), Clicking on menu actions button *Execute PANDAS expressions* of [Plot toolbar widget](#) (page 14).




A dialog box appears *set your pandas expression*. An expression is an python affectation expression ' $df = something$ ', where ' df ' is a pandas dataframe instance displayed in [Contents tab widget](#) (page 15).


¹¹ <https://matplotlib.org>

¹² <https://matplotlib.org>

¹³ http://matplotlib.org/users/navigation_toolbar.html?highlight=toolbar




Scrolling, there are some examples of [PANDAS](https://pandas.pydata.org)¹⁴ dataframe expressions, (read the documentation, sometimes it is **not trivial**).



Users have to type their own expression, and confirm (OK). Do not worry, in case of error(s) in expression, an

¹⁴ <https://pandas.pydata.org>


error dialog box appears.




1.6.2 Example of user plot

When selecting, *for example*, these two columns from ellipse: (X, Z2=X*Y), and Clicking on button 2 of *Plot toolbar widget* (page 14).

Warning: Sometimes, users have to make a **multiple-selection** of *expected* number of columns in *Contents tab widget* **before** plot actions. The order of multiple-selection is significant.



User get this plot



1.7 Tips

1.7.1 Tip 01



Click here to begin new case

1.7.2 Tip 05




Click here to restore your iradina case data

1.7.3 Tip 08




Click here to compute iradina case

1.7.4 Tip 20




Right Click here to get tree expand menu

1.7.5 Tip 25



Right Click here to get contextual menu

1.7.6 Tip 28



▼ ion	
symbolElement	Fe
isotopeNumero	56
atomicNumber	26
atomicWeight	55.454
ionE0	1000
ion	isotope, molar mass (g)
	0

Mouse over to get contextual help tooltip

1.7.7 Tip 30



▼ IonBeam	
▼ ion	
symbolElement	Fe
isotopeNumero	56
atomicNumber	26
atomicWeight	55.454
ionE0	1.000
ion_angle_xy	
▼ Target	

Double left Click here to modify values

1.7.8 Tip 98



Click here to read the iradina-code manual

1.7.9 Tip 99



Click here to read the full-fledged manual

PROGRAMMER'S GUIDE

2.1 Prerequisites

There are some definitions, and links.

1. Iradina¹⁵ code, and its manual.
2. PYTHON¹⁶ 3.5, with packages PyQt5¹⁷, numpy, matplotlib¹⁸, pandas¹⁹, etc. (usually named *py3qt5*).
3. PyInstaller²⁰ 3.4, free software to make iradinaGUI bundle (*only* valid for Linux).
4. 7-zip²¹, free software to compress/uncompress .7z files (for Windows installations).

Installation needs a PYTHON²² 3.6 interpreter, which is included in *All-in-one* iradina installations (Linux *and* Windows). see *Python installation Linux* (page 28).

PyInstaller²³ is a program that freezes Python programs in *bundle*, which is **almost** a python package. For more information about *bundle*, see PyInstaller manual²⁴.

2.2 All-in-one installation

These installations contain in **one** compressed file:

1. the iradinaGUI python scripts.
2. An interpreter PYTHON²⁵.
3. The Iradina code (GPL), its **source files**, and two executable files, one for Linux and one Windows.
4. The useful Corteo²⁶ data base (4bits).

Warning: Corteo data base used version in iradinaGUI is **NOT** Version 20160816.

2.3 All-in-one installation Linux

Warning: This is a PyInstaller²⁷ bundle, installed locally **where users want**. Python interpreter (named *py3qt5*) is simultaneously installed,

Source tar file *iradinaGUI_bundle_xxxx.tgz* is the **one** compressed archive file of the PyInstaller bundle in *one folder* mode. See [more information here](#)²⁸.

There are two ways to install iradinaGUI:

1. Install iradinaGUI directly, using usual *file manager* functionalities: uncompress tar file in user's choice directory.

¹⁵ <https://www.nano.uni-jena.de/en/iradina.html>

¹⁶ <https://docs.python.org/3.5>

¹⁷ <https://pypi.org/project/PyQt5>

¹⁸ <https://matplotlib.org>

¹⁹ <https://pandas.pydata.org>

²⁰ <https://www.pyinstaller.org>

²¹ <https://www.7-zip.org>

²² <https://docs.python.org/3.5>

²³ <https://www.pyinstaller.org>

²⁴ <https://pyinstaller.readthedocs.io/en/stable>

²⁵ <https://docs.python.org/3.5>

²⁶ <http://www.lps.umontreal.ca/~schiette/index.php?n=Recherche.Corteo>

²⁷ <https://www.pyinstaller.org>

²⁸ <https://pyinstaller.readthedocs.io/en/stable/operating-mode.html#bundling-to-one-folder>

2. Install iradinaGUI typing bash command, in usual *terminal*:

```
# install
cd yourChoiceDirectory      # which is really where you want
tar -xf ../iradinaGUI_bundle_XXXX.tgz
# launch
cd iradinaGUI_bundle         # folder name as linux pyinstaller bundle
./iradinaGUI -h               # on line help
./iradinaGUI -g -w ...        # launch GUI
```

2.4 All-in-one installation Windows7-10

Warning:

1. This is **not** a [PyInstaller](https://www.pyinstaller.org)²⁹ bundle.
2. The **mandatory located** root directory is *C:\Users\Public\iradina*.
3. The **mandatory located** iradinaGUI directory is *C:\Users\Public\iradina\iradinaGUI*.
4. The **mandatory located** Python interpreter py3qt5 directory is *C:\Users\Public\iradina\miniconda3*.
5. The software tool to uncompress .7z files is [7-zip](https://www.7-zip.org)³⁰, which **has to be installed**.

Source .7z file *iradinaGUI_XXXX.7z* is the **one** compressed archive file.

There are two ways to install iradinaGUI:

1. Install iradinaGUI directly, using usual *file manager* functionalities: uncompress .7z file in mandatory *C:\Users\Public* directory.
2. Install iradinaGUI typing DOS command, in usual (*Windows7/10-cmd.exe shell*):

```
rem install
C:\
cd C:\Users\Public # this is mandatory location, useful for all users
"C:\Program Files\7-Zip\7z.exe" x ../iradina_XXXX.7z
rem launch
C:\User\Public\iradina\iradinaGUI\LaunchIradinaGUI.bat
```

Note: To launch iradina GUI, you may use Windows shortcut *C:\User\Public\iradina\iradinaGUILaunchIradinaGUI(.lnk)*

²⁹ <https://www.pyinstaller.org>

³⁰ <https://www.7-zip.org>

2.5 Development installations

A development installation of iradinaGUI allows programmer improvements. It is a classical usage of Python³¹ packages. It needs a directory for Python³² interpreter (usually named *miniconda3*), and another directory for iradinaGUI scripts (usually named *iradinaGUI*),

In fine, user could find (and use) command *iradinaGUI* directly after a *detar/unzip* installation. Or a *git clone*.

Warning:

1. **Windows7-10** all-in-one installation is a *development installation* of iradinaGUI, which allows programmer improvements.
2. Users find *miniconda3* and *iradinaGUI* directories in parent directory named *C:\Users\Public\iradina*.
3. **Linux** all-in-one installation *PyInstaller*³³ bundle is **NOT** like that.
4. To get *development installation Linux* (freely located) of iradinaGUI, users have to follow the two next chapters.

2.5.1 Python installation Linux

To install python3 (and its mandatory packages PyQt5 etc.) *locally*, we suggest to use *miniconda*³⁴. Note that *miniconda* is windows7-10 compliant.

Note: You may use this Python interpreter for another python scripting code than iradinaGUI.

For information:

1. <https://conda.io/miniconda.html>
2. <https://conda.io/docs/index.html>

Example of install (*Linux-bash*):

```
bash Miniconda3-latest-Linux-x86_64.sh
# -> Miniconda3 will now be installed into this location:
# -> /volatile/common/miniconda3 (for example. It is located as you want.)
# -> Thank you for installing Miniconda3!

export PATH=/volatile/common/miniconda3/bin:$PATH
which conda
# -> /volatile/common/miniconda3/bin/conda

conda create --name py3qt5 python=3 \
  pip jupyter matplotlib numpy pandas pandas-datareader \
  pyqt=5 scipy sympy jsonschema pyyaml libxml2 paramiko
# -> Solving environment: done
# -> Proceed ([y]/n)? y
# -> Downloading and Extracting Packages
# -> To activate this environment, use:
# -> source activate py3qt5

conda info --envs
# -> conda environments:
```

(continues on next page)

³¹ <https://docs.python.org/3.5>

³² <https://docs.python.org/3.5>

³³ <https://www.pyinstaller.org>

³⁴ <http://conda.pydata.org/miniconda.html>

(continued from previous page)

```
# -> base          /volatile/common/miniconda3
# -> py3qt5        /volatile/common/miniconda3/envs/py3qt5
# -> etc...

source activate py3qt5
which python
# - > /volatile/common/miniconda3/envs/py3qt5/bin/python
```

2.5.2 iradinaGUI installation Linux

Warning: Python interpreter py3qt5 is supposed to be set and useful in environment path. Usually command `source activate py3qt5` assume that.

Example of install/launch (*Linux-bash*):

```
cd whereYouWant
tar -xf ../iradinaGUI_xxxx.tgz
cd iradinaGUI
ls -l iradinaGUI          # the launch executable command (is a script python)
which python              # --> py3qt5
./iradinaGUI -h           # on line help
./iradinaGUI -g -w ...    # launch GUI
```

2.5.3 iradinaGUI installation Windows7-10

Warning: Python interpreter py3qt5 is supposed to be set and useful in environment path, at **mandatory** usual location `C:\Users\Public\iradina\miniconda3`. Usually command `conda activate py3qt5` assume that.

Example of install/launch (*Windows7/10-cmd.exe shell*), using 7-zip³⁵:

```
C:\
cd C:\Users\Public\iradina    # this is mandatory location, useful for all users
"C:\Program Files\7-Zip\7z.exe" x ../iradinaGUI_xxxx.7z
cd C:\Users\Public\iradina\iradinaGUI
where python                  # --> py3qt5
python iradinaGUI -h          # on line help
python iradinaGUI -g -w ...    # launch GUI
```

Note: To launch iradina GUI, you may use Windows shortcut `C:\User\Public\iradina\iradinaGUNLaunchIradinaGUI(.lnk)`.

³⁵ <https://www.7-zip.org>

2.6 IradinaGUI configuration

IradinaGUI uses files to store its configuration parameters. It uses `ConfigParser`³⁶ package, from The Python Standard Library.

Two configuration files are created or used at iradinaGUI launch, and located at `IRADINAGUI_WORKDIR` directory.

1. file `.../IRADINAGUI_WORKDIR/iradinaGUI_user.cfg`
2. file `.../IRADINAGUI_WORKDIR/iradinaGUI_default.cfg`

Note: User may edit/modify file `iradinaGUI_user.cfg`

2.6.1 Syntax

See <https://docs.python.org/3/library/configparser.html>

2.6.2 Description

The effective configuration **is a merge** of these two previous files. Parameters in `iradinaGUI_user.cfg` override parameters in `iradinaGUI_default.cfg`.

User will find **all allowed parameters** in systematically up-to-dated `iradinaGUI_default.cfg`.

³⁶ <https://docs.python.org/3/library/configparser.html>

2.7 Usage of iradinaGUI

2.7.1 Usage

IradaGUI usage is a Command Line Interface (CLI³⁷), which is Windows *and* Linux compatible.

```
iradinaGUI --[options]
```

Options of iradinaGUI

Useful but *not exhaustive* generic options of *iradinaGUI* CLI.

Option **-help** or **-h**

Get help as simple text.

```
iradinaGUI --help           # get list of existing options
```

Option **-doc** or **-d**

Get documentation as browser html.

```
iradinaGUI --doc           # see html doc
```

Option **-verbose** or **-v**

Change verbosity level (default is 'info').

```
# execute iradinaGUI command in verbose debug mode
iradinaGUI -v debug
```

Option **-workdir** or **-w**

Change working directory (user data directory). Default is `../IRADINAGUI_WORKDIR`

```
# execute iradinaGUI in user choice working directory
iradinaGUI -w ../MY_WORKDIR
```

³⁷ https://en.wikipedia.org/wiki/Command-line_interface

2.8 Iradina code compilation

IradaGUI uses a specific version of Iradina code, modified by J.P. Crocombette (cea), which is tagged version 1.1.x for now. This code comes from original version 1.0.8 by Christian Borschel.

Users find two current compiled executable files, which are used by iradinaGUI, located at `.../iradinaGUI/iradinaCode`.

1. `iradina_mingw64.exe`, compiled by [MinGW](http://www.mingw.org)³⁸ gcc compiler, for Windows (64 bits).
2. `iradina_linux64.exe`, compiled by [GNU](https://www.gnu.org/home.en.html)³⁹ gcc⁴⁰ compiler, for Linux (64 bits).

A development installation of Iradina code allows programmer improvements. The following chapters explain Iradina code compilation processes.

2.8.1 Iradina code sources

With GPL licence, sources are available in iradinaGUI directory tree, located at `.../iradinaGUI/iradinaCodes/iradina_cea`.

User find also the useful [Corteo](http://www.lps.umontreal.ca/~schiette/index.php?n=Recherche.Corteo)⁴¹ data base, located at `.../iradinaGUI/iradinaCodes/data_4bit`

```
.../iradinaCodes > tree
.
├── data_4bit
│   ├── 10.asp
│   └── 11.asp
├── etc.
│   ├── corteo.mat
│   └── erfinv.dat
├── doc
│   ├── 20140804_iradina_manual.pdf
│   ├── Corteo20160816.pdf
│   ├── iradina-1-s2.0-S0168583X11006318-main.pdf
│   └── Iradina_tuto_installation.pdf
├── iradina_cea
│   ├── compileIradina.bat
│   ├── fileio.c
│   ├── fileio.h
│   ├── fromcorteo.c
│   ├── fromcorteo.h
│   ├── geometry.c
│   ├── geometry.h
│   ├── indexvalues6bit.h
│   ├── indexvalues.h
│   ├── iradina.c
│   ├── iradina.h
│   ├── license.txt
│   ├── makefile_cea
│   ├── target.c
│   ├── target.h
│   ├── transport.c
│   ├── transport.h
│   ├── utils.c
│   └── utils.h
├── compileIradina.lnk
└── README.txt
```

³⁸ <http://www.mingw.org>

³⁹ <https://www.gnu.org/home.en.html>

⁴⁰ <https://www.gnu.org/software/gcc>

⁴¹ <http://www.lps.umontreal.ca/~schiette/index.php?n=Recherche.Corteo>

2.8.2 Iradina code compilation Linux

Example of compilation (*Linux-bash*):

```
# this is your location
cd ../iradinaGUI/iradinaCodes/iradina_cea
# verifications
cat README.txt
# compilation
make -f makefile_cea clean
make -f makefile_cea iradina
make -f makefile_cea installGUI # install executable in iradinaGUI/iradinaCode
```

2.8.3 Iradina code compilation Windows7-10

Warning:

1. MinGW⁴² is supposed to be set and useful in environment path, at an usual location *C:\MinGW* (for example).
2. Git-windows⁴³ is supposed to be set and useful in environment path, at an usual location *C:\Program Files\Git* (for example). In order to use like-Linux commands.

Example of compilation (*Windows7/10-cmd.exe shell*):

```
# this is mandatory location
C:\
cd C:\Users\Public\iradina\iradinaGUI\iradinaCodes\iradina_cea
# verifications
where make # --> C:\MinGW\bin\make.exe
where gcc # --> C:\MinGW\bin\gcc.exe
where uname # --> C:\Program Files\Git\usr\bin\uname.exe
# compilation
make -f makefile_cea clean
make -f makefile_cea iradina
make -f makefile_cea installGUI # install executable in iradinaGUI/iradinaCode
```

Note: To launch Iradina code compilation, you may use Windows shortcut *C:\User\Public\iradina\iradinaGUT\iradinaCodes\compileIradina(.lnk)*.

⁴² <http://www.mingw.org>

⁴³ <https://git-scm.com>

2.9 Documentation

2.9.1 Doc consultation

To display iradinaGUI html documentation in your web browser *firefox*, or *else*. The initial entry file is located at *iradinaGUI/doc/build/html/index.html*.

```
# Linux bash, as an example
cd ../iradinaGUI
firefox doc/build/html/index.html &
# or as CLI_
iradinaGUI --doc
```

2.9.2 Doc modification

To modify iradinaGUI documentation with simple editor *pluma*, or *else*.

Read the manual, see <http://www.sphinx-doc.org/en/stable/tutorial.html>, or may be copy/paste from ‘Show Source’ item.

```
# Linux bash, as an example
cd ../iradinaGUI/
tmp=$(find doc -name "*.rst")
pluma $tmp &
```

2.9.3 Doc compilation Linux

On a Linux system, to compile iradinaGUI html documentation, programmers use installed GNU⁴⁴ *make*, and SPHINX⁴⁵.

Warning: To make documentation pdf programmers needs installed *texlive* package (preferably up to date version). See: <https://www.tug.org/texlive/quickinstall.html>

```
cd ../iradinaGUI/doc
cat README # read some environment setup information
# ... and read it
make
Please use `make <target>' where <target> is one of
html          to make standalone HTML files
dirhtml       to make HTML files named index.html in directories
singlehtml    to make a single large HTML file
pickle        to make pickle files
json          to make JSON files
htmlhelp      to make HTML files and a HTML help project
qthelp        to make HTML files and a qthelp project
devhelp       to make HTML files and a Devhelp project
epub          to make an epub
latex         to make LaTeX files, you can set PAPER=a4 or PAPER=letter
latexpdf      to make LaTeX files and run them through pdflatex
text          to make text files
man           to make manual pages
changes       to make an overview of all changed/added/deprecated items
linkcheck     to check all external links for integrity
```

(continues on next page)

⁴⁴ <https://www.gnu.org/home.en.html>

⁴⁵ <http://sphinx-doc.org>

(continued from previous page)

```
doctest      to run all doctests embedded in the documentation (if enabled)

# and then
make html      # make html doc
make latexpdf  # make pdf doc
```


FREQUENTLY ASKED QUESTIONS

3.1 Add an Item in this FAQ


Edit *iradinaGUI/doc/src/FAQ.rst* and read documentation *Doc compilation Linux* (page 34).

3.2 FAQ


3.2.1 Why there is NOT all options of Iradina code in IradinaObjects tree ?

Default user mode is set to **simple**, for beginners use.

Select action *change user mode* in contextual menu of *Iradina* node of tree (which is first line/node of tree).



Then Apply as **advanced**.



User can edit/modify value *General.usermode* parameter in the *IradinaGUI configuration* (page 30), to get a permanent setting.

3.2.2 Next question ?

Here there is your next answer etc.

CODE DOCUMENTATION

4.1 Code documentation

4.1.1 iradinapy

iradinapy package

Subpackages

iradinapy.colorama package

Submodules

iradinapy.colorama.ansi module

This module generates ANSI character codes to printing colors to terminals. See: http://en.wikipedia.org/wiki/ANSI_escape_code

class iradinapy.colorama.ansi.**AnsiBack**
Bases: *iradinapy.colorama.ansi.AnsiCodes* (page 40)

BLACK = 40

BLUE = 44

CYAN = 46

GREEN = 42

LIGHTBLACK_EX = 100

LIGHTBLUE_EX = 104

LIGHTCYAN_EX = 106

LIGHTGREEN_EX = 102

LIGHTMAGENTA_EX = 105

LIGHTRED_EX = 101

LIGHTWHITE_EX = 107

LIGHTYELLOW_EX = 103

MAGENTA = 45

RED = 41

RESET = 49

WHITE = 47

YELLOW = 43

class iradinapy.colorama.ansi.**AnsiCodes**
Bases: object

class iradinapy.colorama.ansi.**AnsiCursor**
Bases: object

BACK (*n=1*)

DOWN (*n=1*)

FORWARD (*n=1*)

POS (*x=1, y=1*)

UP (*n=1*)

class iradinapy.colorama.ansi.**AnsiFore**
 Bases: [iradinapy.colorama.ansi.AnsiCodes](#) (page 40)

```
BLACK = 30
BLUE = 34
CYAN = 36
GREEN = 32
LIGHTBLACK_EX = 90
LIGHTBLUE_EX = 94
LIGHTCYAN_EX = 96
LIGHTGREEN_EX = 92
LIGHTMAGENTA_EX = 95
LIGHTRED_EX = 91
LIGHTWHITE_EX = 97
LIGHTYELLOW_EX = 93
MAGENTA = 35
RED = 31
RESET = 39
WHITE = 37
YELLOW = 33
```

class iradinapy.colorama.ansi.**AnsiStyle**
 Bases: [iradinapy.colorama.ansi.AnsiCodes](#) (page 40)

```
BRIGHT = 1
DIM = 2
NORMAL = 22
RESET_ALL = 0
```

```
iradinapy.colorama.ansi.clear_line(mode=2)
iradinapy.colorama.ansi.clear_screen(mode=2)
iradinapy.colorama.ansi.code_to_chars(code)
iradinapy.colorama.ansi.set_title(title)
```

iradinapy.colorama.ansitowin32 module

class iradinapy.colorama.ansitowin32.**AnsiToWin32** (*wrapped,* *convert=None,*
strip=None, autoreset=False)

Bases: object

Implements a 'write()' method which, on Windows, will strip ANSI character sequences from the text, and if outputting to a tty, will convert them into win32 function calls.

```
ANSI_CSI_RE = re.compile('\x01?\x1b\\[(((?:\\d|;)*)([a-zA-Z])\x02?')
ANSI_OSC_RE = re.compile('\x01?\x1b\\[(((?:. |;)*?) (\x07)\x02?')
call_win32(command, params)
```

convert_ansi (*paramstring*, *command*)

convert_osc (*text*)

extract_params (*command*, *paramstring*)

get_win32_calls ()

reset_all ()

should_wrap ()

True if this class is actually needed. If false, then the output stream will not be affected, nor will win32 calls be issued, so wrapping stdout is not actually required. This will generally be False on non-Windows platforms, unless optional functionality like autoreset has been requested using kwargs to `init()`

write (*text*)

write_and_convert (*text*)

Write the given text to our wrapped stream, stripping any ANSI sequences from the text, and optionally converting them into win32 calls.

write_plain_text (*text*, *start*, *end*)

class `iradinapy.colorama.ansitowin32.StreamWrapper` (*wrapped*, *converter*)

Bases: `object`

Wraps a stream (such as `stdout`), acting as a transparent proxy for all attribute access apart from method `'write()'`, which is delegated to our `Converter` instance.

write (*text*)

`iradinapy.colorama.ansitowin32.is_a_tty` (*stream*)

`iradinapy.colorama.ansitowin32.is_stream_closed` (*stream*)

iradinapy.colorama.initialise module

`iradinapy.colorama.initialise.colorama_text` (**args*, ***kwargs*)

`iradinapy.colorama.initialise.deinit` ()

`iradinapy.colorama.initialise.init` (*autoreset=False*, *convert=None*, *strip=None*,
wrap=True)

`iradinapy.colorama.initialise.reinit` ()

`iradinapy.colorama.initialise.reset_all` ()

`iradinapy.colorama.initialise.wrap_stream` (*stream*, *convert*, *strip*, *autoreset*, *wrap*)

iradinapy.colorama.win32 module

`iradinapy.colorama.win32.SetConsoleTextAttribute` (*)

`iradinapy.colorama.win32.winapi_test` (*)

iradinapy.colorama.winterm module

```
class iradinapy.colorama.winterm.WinColor
    Bases: object

    BLACK = 0
    BLUE = 1
    CYAN = 3
    GREEN = 2
    GREY = 7
    MAGENTA = 5
    RED = 4
    YELLOW = 6

class iradinapy.colorama.winterm.WinStyle
    Bases: object

    BRIGHT = 8
    BRIGHT_BACKGROUND = 128
    NORMAL = 0

class iradinapy.colorama.winterm.WinTerm
    Bases: object

    back (back=None, light=False, on_stderr=False)
    cursor_adjust (x, y, on_stderr=False)
    erase_line (mode=0, on_stderr=False)
    erase_screen (mode=0, on_stderr=False)
    fore (fore=None, light=False, on_stderr=False)
    get_attrs ()
    get_position (handle)
    reset_all (on_stderr=None)
    set_attrs (value)
    set_console (attrs=None, on_stderr=False)
    set_cursor_position (position=None, on_stderr=False)
    set_title (title)
    style (style=None, on_stderr=False)
```

Module contents

iradinapy.example package

Submodules

iradinapy.example.essai_logging_1 module

<http://sametmax.com/ecrire-des-logs-en-python/> <https://docs.python.org/3/library/time.html#time.strftime>

essai utilisation logger plusieurs handler format different

```
/usr/lib/python2.7/logging/__init__.pyc
```

```
init MyLogger, fmt='%asctime)s :: %(levelname)-8s :: %(message)s', level='20'
```

```
2018-03-11 18:51:21 :: INFO :: test logger info 2018-03-11 18:51:21 :: WARNING :: test logger
warning 2018-03-11 18:51:21 :: ERROR :: test logger error 2018-03-11 18:51:21 :: CRITICAL ::
test logger critical
```

```
init MyLogger, fmt='None', level='10'
```

```
2018-03-11 18:51:21 :: DEBUG :: test logger debug test logger debug 2018-03-11 18:51:21 :: INFO
:: test logger info test logger info 2018-03-11 18:51:21 :: WARNING :: test logger warning test logger
warning 2018-03-11 18:51:21 :: ERROR :: test logger error test logger error 2018-03-11 18:51:21 ::
CRITICAL :: test logger critical test logger critical
```

```
iradinapy.example.essai_logging_1.getMyLogger()
```

```
iradinapy.example.essai_logging_1.initMyLogger (fmt=None, level=None)
```

```
iradinapy.example.essai_logging_1.testLogger1()
```

iradinapy.example.essai_logging_2 module

<http://sametmax.com/ecrire-des-logs-en-python/> <https://docs.python.org/3/library/time.html#time.strftime>

essai utilisation logger un handler format different sur info() pas de format et su other format

```
/usr/lib/python2.7/logging/__init__.pyc
```

```
init MyLogger, fmt='%asctime)s :: %(levelname)-8s :: %(message)s', level='20'
```

```
test logger info 2018-03-11 18:51:51 :: WARNING :: test logger warning 2018-03-11 18:51:51 ::
ERROR :: test logger error 2018-03-11 18:51:51 :: CRITICAL :: test logger critical
```

```
class iradinapy.example.essai_logging_2.MyFormatter (fmt=None,    datefmt=None,
                                                    style='%')
```

Bases: logging.Formatter

format (record)

Format the specified record as text.

The record's attribute dictionary is used as the operand to a string formatting operation which yields the returned string. Before formatting the dictionary, a couple of preparatory steps are carried out. The message attribute of the record is computed using LogRecord.getMessage(). If the formatting string uses the time (as determined by a call to usesTime(), formatTime() is called to format the event time. If there is exception information, it is formatted using formatException() and appended to the message.

```
iradinapy.example.essai_logging_2.getMyLogger()
```

```
iradinapy.example.essai_logging_2.initMyLogger (fmt=None, level=None)
```

```
iradinapy.example.essai_logging_2.testLogger1()
```


Module contents

Submodules

iradinapy.abcdExpression module

from '3(a2bc)' to 'abbcabbcabbc' without regexp, not recursive for not smart poor people

`iradinapy.abcdExpression.getIndicesFromChar (aChar)`
returns 0 for 'a', 1 for 'b' etc., max is 'z'

`iradinapy.abcdExpression.toAbcd (aStr, verbose=False, details=False)`
'10(abc)' to return '10*(a+b+c)' raise exception if problem

`iradinapy.abcdExpression.toEval0123 (aStr, verbose=False)`
'3(a2bc)' to return [0,1,1,2,0,1,1,2,0,1,1,2] for 'abbcabbcabbc' raise exception if problem

`iradinapy.abcdExpression.toEvalAbcd (aStr, verbose=False)`
'3(a2bc)' to return 'abbcabbcabbc' raise exception if problem

`iradinapy.abcdExpression.toEvalAbcdForTooltip (aStr, length=20)`
set results in length characters lines

iradinapy.analysisIra module

```
class iradinapy.analysisIra.AnalysisIra
    Bases: xyzpy.baseXyz._XyzConstrainBase
    appendHistoryFileManager (action)
    createDocLaunch ()
    getActionsContextMenu ()
    gitCommit ()
    gitkLaunch ()
    isHidden (nameAttr)
        to know if attribute is currently displayed in treeView and other dialog widget
    packageLaunch ()
    postTreatments ()
    printROOTContext ()
    runPythonCode ()
    searchURANIEMethod ()
    setDefaultValues ()
        not virtual, could be used
    toFileIra ()
    updateRootlogonLaunch ()

class iradinapy.analysisIra.AttributeDataFrameIra (value=None)
    Bases: xyzpy.intFloatListXyz.StrXyz
    drawGraphic ()
    drawUnivariate ()
    getActionsContextMenu ()
    getAttributeName ()
```

```

getExpressionsInParent ()

getFileInParent ()

class iradinapy.analysisIra.DataInformationsIra
    Bases: xyzpy.baseXyz._XyzConstrainBase
    general informations about

    getEtudeWorkdir ()
        return as os.path.join(directory,name)

    getEtudeWorkdirBrut ()
        return as ${IRADINAGUI_WORKDIR}

    getVersion ()

    isHidden (nameAttr)
        to know if attribute is currently displayed in treeView and other dialog widget

    setDefaultValues ()
        not virtual, could be used

class iradinapy.analysisIra.DataIra
    Bases: xyzpy.baseXyz._XyzConstrainBase
    DataFrame

    copyFileInData ()

    drawDialogDataServer ()

    getActionsContextMenu ()

    getAllAttributesName ()

    getNameExpanded ()

    setAttributes ()
        append attributes from '#COLUMN_NAMES' from file .dat, ordered as useful in uranie

class iradinapy.analysisIra.DataManagerIra (nameObject="")
    Bases: iradinapy.analysisIra.ListOfFileViewerXyz (page 47)

    copyAllFileInData ()

    getActMenu ()

class iradinapy.analysisIra.ExpressionIra (value=None)
    Bases: xyzpy.intFloatListXyz.ExpressionXyz

    createEditorData (parent=None)

    drawGraphic ()

    drawUnivariate ()

    getActionsContextMenu ()
        no browse

    getAllAttributesNameInParents ()

    getAttributeName ()
        synonym for coherency with AttributeIra

    getExpressionsInParent ()

    getFileInParent ()

    getName ()

    isNameUnique (name)
        test unicity of name in DataIra search in lists DataIra.attributes and DataIra.expressions

```

```

isValidExpression (value)
    test if expression is valid in a uranie TDataServer

class iradinapy.analysisIra.FileIra (value=None)
    Bases: xyzpy.intFloatListXYZ.FileViewerXYZ

    initialize type of files extension for interest .C etc.

class iradinapy.analysisIra.FunctionIra (value=None)
    Bases: iradinapy.analysisIra.FileIra (page 47)

    initialize type of files extension for function files

class iradinapy.analysisIra.HistoryFileManagerXYZ
    Bases: xyzpy.baseXYZ._XYZConstrainBase

    store in string for xml save history on some files, with hashing control as cp, mv etc... actions from
    gui/model actions one line by action

    appendHistoryAction (action)

    appendHistoryCopyOf (originFile, newFile)

    clearHistory ()

    getCompleteFileName (aFile)

    getFileHash (aFile)

    getIdentFile (aFile)

    isHidden (nameAttr)
        to know if attribute is currently displayed in treeView and other dialog widget

    setDefaultValues ()
        not virtual, could be used

class iradinapy.analysisIra.LibraryIra (value=None)
    Bases: iradinapy.analysisIra.FileIra (page 47)

    initialize type of files extension for libraries files .C .so

class iradinapy.analysisIra.ListOfAttributeIra (nameObject="")
    Bases: xyzpy.baseXYZ.ListOfBaseXYZ

    getAllAttributesName ()

class iradinapy.analysisIra.ListOfExpressionIra (nameObject="")
    Bases: xyzpy.baseXYZ.ListOfBaseXYZ

    getAllAttributesName ()

    getExpressions ()

class iradinapy.analysisIra.ListOfFileViewerXYZ (nameObject="")
    Bases: xyzpy.baseXYZ.ListOfBaseXYZ

    base class, used only inheritance, modify _allowedClasses etc

    addItem (aClass=None)
        override method ListOfBaseXYZ

    addItems (aClass=None)

    addItemsSlot (status, aClass=None)
        new pyqt5 state override in lambda

    browseViewerDialog ()

    browseViewerExecOnApply (selectedFiles)
        part of Apply on browseViewerDialog

    getActionsContextMenu ()

```

```

getDirectory ()
    could be dynamic in inheritance

getNamesExpanded ()

getNoLocal ()

getTargetDirectory ()
    could be dynamic in inheritance

class iradinapy.analysisIra.ListOfFunctionIra (nameObject="")
    Bases: iradinapy.analysisIra.ListOfFileViewerXyz (page 47)

class iradinapy.analysisIra.ListOfLibraryIra (nameObject="")
    Bases: iradinapy.analysisIra.ListOfFileViewerXyz (page 47)

class iradinapy.analysisIra.ListOfMacroIra (nameObject="")
    Bases: iradinapy.analysisIra.ListOfFileViewerXyz (page 47)

class iradinapy.analysisIra.ListOfUserFileIra (nameObject="")
    Bases: iradinapy.analysisIra.ListOfFileViewerXyz (page 47)

getDirectory ()
    dynamic override _directory

getTargetDirectory ()
    dynamic override _targetDirectory

class iradinapy.analysisIra.MacroIra (value=None)
    Bases: iradinapy.analysisIra.FileIra (page 47)

    initialize type of files extension for macro .C .py

class iradinapy.analysisIra.MacroManagerIra
    Bases: xyzpy.baseXyz._XyzConstrainBase

getNamesExpanded ()

getNoLocal ()

setDefaultValues ()
    not virtual, could be used

class iradinapy.analysisIra.UserFileIra (value=None)
    Bases: xyzpy.intFloatListXyz.FileViewerXyz

    initialize type of files extension for user interest

iradinapy.analysisIra.drawGraphic (self)
    common method draw histogram for classes as AttributeIra or ExpressionIra

iradinapy.analysisIra.drawUnivariate (self)
    common method draw univariate for classes as AttributeIra or ExpressionIra

iradinapy.analysisIra.fn_heterogenous_random_multiple_materials (case, aStream)

iradinapy.analysisIra.fn_homogenous_one_material (case, aStream, options={})

iradinapy.analysisIra.fn_multiLayer_multiple_materials (case, aStream, options={})

iradinapy.analysisIra.getCurrentRowColumn (indiceCurrent, nbmaxGrid, rowBefore=True)
    returns current (row, column) in nbmax elements in grid for indice current (0 to nbmaxGrid)

iradinapy.analysisIra.getDefaultRowColumn (nb)
    return (row, column)

```

```

iradinapy.analysisIra.getRandomConcMaterial (irandoms)
    returns random indice in Materials (using TargetConcentration) irandoms is list as cumul of TargetConcentration

iradinapy.analysisIra.get_value_random_multiple_materials (case)
    return random value for integer indice in Materials using getRandomConcMaterial

iradinapy.analysisIra.join (*v)
    as os.path.join but set antislash as slash, even for windows, keep windows 'c:'

iradinapy.analysisIra.normalize (aList)

iradinapy.analysisIra.toFileCompositionIn (case, aStream, name)
    see 'Creating new composition file' line 1222 in utils.C

iradinapy.analysisIra.toFileConfigurationIn (case, aStream, name="")

iradinapy.analysisIra.toFileMaterialIn (case, aStream, name="")

iradinapy.analysisIra.toFileStructureIn (case, aStream, name="")

iradinapy.analysisIra.toValue (aStr, name, value)

```

iradinapy.caseIradina module

```

class iradinapy.caseIradina.BeamSpreadIra (value=None)
    Bases: xyzpy.intFloatListXyz.FloatPosXyz
    float positive with default 1.

class iradinapy.caseIradina.BoolFalseIra (value=None)
    Bases: xyzpy.intFloatListXyz.BoolXyz
    ['False', 'True'] with write config file iradina strCfg [0, 1] default False
    strCfg()

class iradinapy.caseIradina.BoolTrueIra (value=None)
    Bases: iradinapy.caseIradina.BoolFalseIra (page 49)
    ['False', 'True'] with write config file iradina strCfg [0, 1] default True

class iradinapy.caseIradina.CaseIra
    Bases: xyzpy.baseXyz._XyzConstrainBase
    general informations about case and for launch iradina
    isHidden (nameAttr)
        to know if attribute is currently displayed in treeView and other dialog widget
    setDefaultValues()
        not virtual, could be used

class iradinapy.caseIradina.CellCountxIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntSupEq1Xyz
    int positive with default 100

class iradinapy.caseIradina.CellCountyIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntSupEq1Xyz
    int positive with default 1

class iradinapy.caseIradina.CellCountzIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntSupEq1Xyz
    int positive with default 1

```

```

class iradinapy.caseIradina.CellDepthxIra (value=None)
    Bases: xyzpy.intFloatListXyz.FloatPosXyz
    float positive with default 1000. (nm)

    toXml (**kwargs)
        set tooltip_1 attribute xml for tooltip as long name element (value column 1)

class iradinapy.caseIradina.CellMultiLayerxIra (value=None)
    Bases: xyzpy.intFloatListXyz.StrXyz
    'abcd' values for multiLayer description

    getCount ()
        returns len(self) as 8 for '2(abcd)'

    getIndicesFromChar (aChar)
        returns 0 for 'a', 1 for 'b' etc.

    getMultiLayerMaterial (indice, verbose=False)

    toEval0123 ()
        returns [0,1,2,3,0,1,2,3] for '2(abcd)'

    toEvalAbcd ()
        returns 'abcdabcd' for '2(abcd)'

class iradinapy.caseIradina.CellSizexIra (value=None)
    Bases: xyzpy.intFloatListXyz.FloatPosXyz
    float positive with default 10.

class iradinapy.caseIradina.CellSizeyIra (value=None)
    Bases: xyzpy.intFloatListXyz.FloatPosXyz
    float positive with default 100.

class iradinapy.caseIradina.CellSizezIra (value=None)
    Bases: xyzpy.intFloatListXyz.FloatPosXyz
    float positive with default 100.

class iradinapy.caseIradina.CompositionFileTypeIra (value=None)
    Bases: xyzpy.intFloatListXyz.StrInListXyz

    If the file is just one column of values then FileType should be set to 1. If the file contains 4 columns (x, y,
    z, value) then set it to 0.

    strCfg ()
        get index from '(i) blah blah'

class iradinapy.caseIradina.ConcentrationIra (value=None, minMax=None)
    Bases: xyzpy.intFloatListXyz.FloatRangeXyz
    initial value as 1.

class iradinapy.caseIradina.DensityIra (value=None)
    Bases: xyzpy.intFloatListXyz.FloatPosXyz
    float positive with default 0. supposed g/cm3, have to convert to at/cm3

    getActionsContextMenu ()
        append action 'Set default value'

    getCalculatedValue ()
        prorata ElementConc(s) and Components densities a trivial approximation

    normalize (aList)

    setCalculatedValue ()

```

```

strCfg ()
    iradina needs density of the material in atoms/cm3

toAtomCm3 ()
    prorata ElementConc(s) and Components atomic weights

toXml (**kwargs)
    set tooltip_1 attribute xml for tooltip as long name element (value column 1)

class iradinapy.caseIradina.DensityTargetComponentIra (value=None)
    Bases: xyzpy.intFloatListXyz.FloatPosXyz
    TODO could set default density from wiki localMendeleiev or user config

getActionsContextMenu ()
    append action 'Set default value'

getUserConfigValue ()

getWikipediaValue ()

setDefaultDensityUser ()

setDefaultDensityWiki ()

class iradinapy.caseIradina.DisplayIntervalIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntSupEq1Xyz
    int positive with default 20

class iradinapy.caseIradina.ElementCountIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntRangeXyz
    as define MAX_NO_MATERIALS 20 as Maximum number of different materials

class iradinapy.caseIradina.ElementReplEnergyIra (value=None)
    Bases: xyzpy.intFloatListXyz.FloatXyz
    float positive with default value -1 as None

class iradinapy.caseIradina.FlightLengthTypeIra (value=None)
    Bases: xyzpy.intFloatListXyz.StrInListXyz

strCfg ()
    get index from '(i) blah blah'

class iradinapy.caseIradina.FloatListIra (value=None)
    Bases: xyzpy.intFloatListXyz.StrXyz
    accept [val1, val2, val3]

class iradinapy.caseIradina.IonAngleIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntRangeXyz
    angle incidence xy (degree) integer range -90 to 90 default 0.

toVx ()

toVy ()

toXml (**kwargs)
    kwarg are for optional future option of added details in xml tree

class iradinapy.caseIradina.IonBeamIra
    Bases: xyzpy.baseXyz._XyzConstrainBase
    general informations about beam iradina

isHidden (nameAttr)
    to know if attribute is currently displayed in treeView and other dialog widget

```

```

class iradinapy.caseIradina.IonDistributionIra (value=None)
    Bases: xyzpy.intFloatListXYZ.StrInListXYZ

    strCfg ()
        get index from '(i) blah blah'

class iradinapy.caseIradina.IonDoseIra (value=None)
    Bases: xyzpy.intFloatListXYZ.FloatXYZ

    float positive with default value -1 as None

class iradinapy.caseIradina.IonE0Ira (value=None)
    Bases: xyzpy.intFloatListXYZ.FloatPosXYZ

    float positive with default 10e3 keV

class iradinapy.caseIradina.IonMIra (value=None)
    Bases: xyzpy.intFloatListXYZ.FloatPosXYZ

    Ion mass (g/mol) float positive with default 1.

class iradinapy.caseIradina.IonVxIra (value=None)
    Bases: xyzpy.intFloatListXYZ.FloatPosXYZ

    vector incidence x float positive with default 1.

class iradinapy.caseIradina.IonVyIra (value=None)
    Bases: xyzpy.intFloatListXYZ.FloatPosXYZ

    vector incidence y float positive with default 0.

class iradinapy.caseIradina.IonVzIra (value=None)
    Bases: xyzpy.intFloatListXYZ.FloatPosXYZ

    vector incidence z float positive with default 0

class iradinapy.caseIradina.IsotopeIra
    Bases: xyzpy.baseXYZ._XYZConstrainBase

    general informations about IsotopeIra

    browseElement ()

    checkValues (verbose=True)

    getActionsContextMenu ()
        append action 'Append file projectile'

    isHidden (nameAttr)
        to know if attribute is currently displayed in treeView and other dialog widget

    on_attributesChange (verbose=False)

    setDefaultValues ()
        not virtual, could be used

class iradinapy.caseIradina.ListOfMaterialIra (nameObject="")
    Bases: xyzpy.baseXYZ.ListOfBaseXYZ

    Important note: it is strongly recommended NOT to create one file with all materials that you know for
    all of your simulations! You should just include the materials you really need for the current simulation,
    because iradina will create 2.6 MByte scattering matrices for every possible combination of two elements
    in the target! So the memory usage increases with the square of the number of different elements! If your
    materials contain 92 different elements, iradina needs 22 GByte of memory in the 4-MSB version or 352
    GByte in the 6-MSB version

    getAllAttributesName ()

class iradinapy.caseIradina.ListOfTargetComponentsIra (nameObject="")
    Bases: xyzpy.baseXYZ.ListOfBaseXYZ

```



```

class iradinapy.caseIradina.MaterialIra
    Bases: xyzpy.baseXyz._XyzConstrainBase
    general informations about material of target iradina

    getElementCount ()
    getElementsConc ()
    getElementsDispEnergy ()
    getElementsLattEnergy ()
    getElementsM ()
    getElementsReplEnergy ()
    getElementsSurfEnergy ()
    getElementsSymbol ()
    getElementsZ ()
    isHidden (nameAttr)
        to know if attribute is currently displayed in treeView and other dialog widget
    normalize (aList)

class iradinapy.caseIradina.MaterialNameIra (value=None)
    Bases: xyzpy.intFloatListXyz.StrXyz
    string no more 24 characters target.c: if(strlen(MaterialName)>=25){MaterialName[24]=';'}

class iradinapy.caseIradina.MaxNoIonIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntPosXyz
    int positive with default 20000

class iradinapy.caseIradina.MinEnergyIra (value=None)
    Bases: xyzpy.intFloatListXyz.FloatPosXyz
    float positive with default 5.

class iradinapy.caseIradina.NormalizeOutputIra (value=None)
    Bases: xyzpy.intFloatListXyz.StrInListXyz
    strCfg ()
        get index from '(i) blah blah'

class iradinapy.caseIradina.Seed1Ira (value=None)
    Bases: xyzpy.intFloatListXyz.IntPosXyz
    int positive with default 123

class iradinapy.caseIradina.Seed2Ira (value=None)
    Bases: xyzpy.intFloatListXyz.IntPosXyz
    int positive with default 456

class iradinapy.caseIradina.SeedIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntPosXyz
    python random.seed(a=None) to initialize internal state of the random number generator as None or no
    argument seeds from current time or from an operating system specific randomness source if available

class iradinapy.caseIradina.SimulationIra
    Bases: xyzpy.baseXyz._XyzConstrainBase
    general informations about simulation iradina

    isHidden (nameAttr)
        to know if attribute is currently displayed in treeView and other dialog widget

```

```

class iradinapy.caseIradina.SimulationTypeIra (value=None)
    Bases: xyzpy.intFloatListXyz.StrInListXyz

    strCfg ()
        get index from '(i) blah blah'

class iradinapy.caseIradina.StatusUpdateIntervalIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntPosXyz

    int positive with default 10000

class iradinapy.caseIradina.StorageIntervalIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntPosXyz

    int positive with default 2000

class iradinapy.caseIradina.StorePathLimitIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntSupEq1Xyz

    int positive with default 50

class iradinapy.caseIradina.StorePathLimitRecoilsIra (value=None)
    Bases: xyzpy.intFloatListXyz.IntXyz

    int positive with default -1 as None

class iradinapy.caseIradina.StragglngModelIra (value=None)
    Bases: xyzpy.intFloatListXyz.StrInListXyz

    strCfg ()
        get index from '(i) blah blah'

class iradinapy.caseIradina.StructureIra
    Bases: xyzpy.baseXyz._XyzConstrainBase

    general informations about target iradina

    getCellSizeX ()

    getMultiLayerMaterial (indice)

    get_cell_count_x ()

    isHidden (nameAttr)
        to know if attribute is currently displayed in treeView and other dialog widget

class iradinapy.caseIradina.TargetComponentIra
    Bases: xyzpy.baseXyz._XyzConstrainBase

    general informations about TargetComponentIra

    browseElement ()

    checkValues (verbose=True)

    getActionsContextMenu ()
        append action 'Append file projectile'

    isHidden (nameAttr)
        to know if attribute is currently displayed in treeView and other dialog widget

    on_attributesChange (verbose=False)

    setDefaultValues ()
        not virtual, could be used

class iradinapy.caseIradina.TargetIra
    Bases: xyzpy.baseXyz._XyzConstrainBase

    general informations about target iradina

```

isHidden (*nameAttr*)

to know if attribute is currently displayed in treeView and other dialog widget

class iradinapy.caseIradina.**TypeCompositionIra** (*value=None*)

Bases: xyzpy.intFloatListXyz.StrInListXyz

strCfg ()

get info

iradinapy.coloringIra module

simple tagging as '<color>' for simple coloring log messages on terminal(s) window or unix or ios using backend colorama. Using '<color>' because EZ human readable, So '<color>' are not supposed existing in log message. "{ }".format() is not choosen because "{ }" are present in log messages of contents of python dict (as JSON) etc.

Usage:

```
>> import iradinapy.coloringIra as COLS
```

Example:

```
>> log("this is in <green>color green<reset>, OK is in blue: <blue>OK?")
```

class iradinapy.coloringIra.**ColoringStream**

Bases: object

write my stream class only write and flush are used for the streaming <https://docs.python.org/2/library/logging.handlers.html> <https://stackoverflow.com/questions/31999627/storing-logger-messages-in-a-string>

flush ()

write (*astr*)

iradinapy.coloringIra.**cleanColors** (*msg*)

clean the message of color tags '<red>' ...

iradinapy.coloringIra.**indent** (*msg, nb, car=' '*)

indent nb car (spaces) multi lines message except first one

iradinapy.coloringIra.**log** (*msg*)

elementary log stdout for debug if _verbose

iradinapy.coloringIra.**replace** (*msg, tags*)

iradinapy.coloringIra.**toColor** (*msg*)

automatically clean the message of color tags '<red>' ... if the terminal output stdout is redirected by user if not, replace tags with ansi color codes

iradinapy.coloringIra.**toColor_AnsiToWin32** (*msg*)

for test debug no wrapping

iradinapy.configIra module

This file is the main API for config configparser for iradinaGUI

class iradinapy.configIra.**ConfigManager** (*runner*)

Bases: object

Manages the read/write of config files of iradinaGUI, and merges if useful.

file iradinaGUI_user.cfg

file iradinaGUI_default.cfg

assertUserDefaultFiles ()

if inexistent, create config files user and default. relative to workdir

checkFileExist (*filename*)

filename as name relative to workdir

getDefaultConfig ()

new instance default config

getMainConfig ()

main as merged config of default plus overrides of user new instance main config

getRealPath (*name*)

getUserConfig ()

new instance user config

getWorkdir ()

setMainConfig (*cfg*)

set a user main config as global, is user choice

iradinapy.configIra.**getCurrentMode** ()

iradinapy.configIra.**getExistingModes** ()

iradinapy.configIra.**getMainConfig** ()

iradinapy.configIra.**isHidden** (*item, nameAttr=None, modeName=None*)

avoid Components[*].Density because fnmatch pattern [seq] matches any character in seq. use Components*.Density instead

iradinapy.configIra.**setCurrentMode** (*modeName*)

iradinapy.controlSimulationIra module

class iradinapy.controlSimulationIra.**ControlSimulationIra**

Bases: xyzpy.baseXyz._XyzConstrainBase

general informations about

setDefaultValues ()

not virtual, could be used

class iradinapy.controlSimulationIra.**UserModeIra** (*value=None*)

Bases: xyzpy.intFloatListXyz.StrInListXyz

iradinapy.controllerIra module

```
iradinapy.controllerIra.join(*v)
    as os.path.join but set antislash as slash, even for windows, keep windows 'c:'

iradinapy.controllerIra.launchFromSalomePyConsole()
```

iradinapy.dateTime module

This file contains DateTime and DeltaTime class

Usage:

```
>> import dateTime as DATT
>> ini = DATT.DateTime("now")
>> # some stuff
>> fin = DATT.DateTime("now")
>> duration = DATT.DeltaTime(ini, fin)
```

```
class iradinapy.dateTime.DateTime(when=None)
    Bases: object
    assume storing a date and hour, and conversions
```

Usage:

```
>> import dateTime as DATT
>> now = DATT.DateTime("now")
>> print("now is %s" % now)
```

```
FORMAT_DATEHOUR_CONFIG = '%Y%m%d_%H%M%S'
```

```
FORMAT_DATE_CONFIG = '%Y%m%d'
```

```
FORMAT_FILE = '%Y%m%d_%H%M%S'
```

```
FORMAT_HOUR_CONFIG = '%H%M%S'
```

```
FORMAT_HUMAN = '%Y-%m-%d %H:%M:%S'
```

```
FORMAT_PACKAGE = '%Y-%m-%d %H:%M'
```

```
FORMAT_XML = '%Y/%m/%d %Hh%Mm%Ss'
```

```
MSG_UNDEFINED = 'UndefinedTime'
```

```
addSeconds(secs)
    add seconds at time
```

```
getSecondsToNow()
```

```
getValue()
```

```
isOk()
    return True if ok
```

```
localTime()
```

```
raiseIfKo()
    raise an exception with message why if not ok, else return self. This trick is to write usage
```

Usage:

```
>> aTimeOk = aTime.raiseIfKo() # raise Exception if KO
>> doSomethingWithaTimeOk(aTimeOk) # here i am sure that is OK
```

setValue (*time*)

choice as not deep copying if mutables value

toSeconds ()

toStrDateConfig ()

toStrDateHourConfig ()

toStrFile ()

use self.FORMAT_FILE, sortable, 2018-05-07... as '20180507_235958'

toStrHourConfig ()

toStrHuman ()

use self.FORMAT_HUMAN

toStrPackage ()

toStrXml ()

class iradinapy.dateTime.DeltaTime (*t1=None, t2=None*)

Bases: object

assume storing a duration, delta between two DateTime, and conversions

Usage:

```
>> import dateTime as DATT
>> t1 = DATT.DateTime("now")
>> time.sleep(3)
>> t2 = DATT.DateTime("now")
>> delta = DATT.DeltaTime(t1, t2)
>> print("delta time is %s" % delta)
```

MSG_UNDEFINED = 'UndefinedDeltaTime'

getT1 (*t*)

getT2 (*t*)

getValue ()

idem toSeconds()

isOk ()

return True if ok

raiseIfKo ()

raise an exception with message why if not ok, else return self. This trick is to write usage

Usage:

```
>> aDeltaTimeOk = adeltaTime.raiseIfKo() # raise Exception if KO
>> doSomethingWithaDeltaTimeOk(aDeltaTimeOk) # here i am sure that is OK
```

setT1 (*t*)

setT2 (*t*)

toMinutes ()

toSeconds ()

toStrHms ()
all unities, hours and minutes and seconds as '2h34m56s'

toStrHuman ()
automatic best unity, hours or minutes or seconds

iradinapy.dateTime.date_to_datetime (date)
From a string date as pyconf config.VARS.datehour 'YYYYMMDD_HHMMSS' returns [year, month, day, hour, minutes, seconds]

Parameters **date** – (str) The date in format YYYYMMDD_HHMMSS

Returns (tuple) as (str,str,str,str,str,str) The same date and time in separate variables.

iradinapy.dateTime.fromDateHourConfig (datehour)
datehour as pyconf config.VARS.datehour 'YYYYMMDD_HHMMSS'. Returns datetime.datetime

iradinapy.dateTime.fromTimeStamp (val)
Returns datetime.datetime

iradinapy.dateTime.getWeekDayNow ()
Returns monday as 0, tuesday as 1 etc.

iradinapy.dateTime.parse_date (date)
Transform as pyconf config.VARS.datehour 'YYYYMMDD_HHMMSS' to 'YYYY-MM-DD hh:mm:ss'.

Parameters **date** – (str) The date to transform

Returns (str) The date in the new format

iradinapy.dateTime.sleep (seconds)
as time.sleep(seconds)

iradinapy.dateTime.timedelta_total_seconds (timedelta)
Replace total_seconds from datetime module in order to be compatible with old python versions

Parameters **timedelta** – (datetime.timedelta) The delta between two dates

Returns (float) The number of seconds corresponding to timedelta.

iradinapy.iradinaFilePatterns module

all file patterns of supposedly (sometimes) created by iradinaGui replaces '@xxx@' as file.in autotools

iradinapy.iradinaFilePatterns.execReplaces (aStr, replaces=[])
append standart useful replaces to users replaces

iradinapy.iradinaFilePatterns.filterColumnsNamesForUranie (header)
assume inexistent header array with empty strings '' lenght of #COLUMN_NAMES fill incomplete array with ''

iradinapy.iradinaFilePatterns.filterHeaderDat (line)
extract (key, value) from line from file .dat uranie/salome/paraview

iradinapy.iradinaFilePatterns.getBaseFiles ()
list of useful mandatory files in uranie etude directory

iradinapy.iradinaFilePatterns.getDefaultDivide (nb)
Canvas.Divide by default

iradinapy.iradinaFilePatterns.getFilePatterns (name, replaces=[])

iradinapy.iradinaFilePatterns.getFixedUsefulDirs (rootDir)
unconditionally fixed useful

```

iradinapy.iradinaFilePatterns.getHeaderContentsFileDat (filenameIni)
    header description of .dat uranie/salome/paraview returns a dict with keys NAME,DATE... message if
    inexisting file

iradinapy.iradinaFilePatterns.getHeaderFileDat (filename, Verbose=False)
    header description of .dat uranie/salome/paraview returns a dict with keys #NAME, #DATE...

iradinapy.iradinaFilePatterns.getIgnoreFilesForCpack (rootDir, useful, Ver-
                                                    bose=False)
    list of useless directories in uranie etude directory, not packaging saved

iradinapy.iradinaFilePatterns.getOtherUsefulDirsForCpack (rootDir)
    unconditionally fixed useful are not in other useful directories get user subdirs with CMakeLists.txt as useful

iradinapy.iradinaFilePatterns.getPatternKeys ()

iradinapy.iradinaFilePatterns.getStdReplaces ()
    standart useful replaces, @xxx@ as .in autotools

iradinapy.iradinaFilePatterns.getTypesOfVisualize ()

iradinapy.iradinaFilePatterns.getUsefulDirsForCpack (rootDir)

iradinapy.iradinaFilePatterns.getUselessDirsForCpack (rootDir)
    list of useless directories in uranie etude directory, not packaging saved

iradinapy.iradinaFilePatterns.getUselessFilesForCpack (rootDir, useful)
    list of useless files in uranie etude directory, not packaging saved

iradinapy.iradinaFilePatterns.getVisualizeMethod (aName)

iradinapy.iradinaFilePatterns.isPresentCMakeLists (aDir)
    test if CMakeLists.txt exists in directory

iradinapy.iradinaFilePatterns.isUranieColumn (name)

iradinapy.iradinaFilePatterns.listOnlyDirs (rootDir)
    return list of expanded directories names in directory

iradinapy.iradinaFilePatterns.removeDuplicates (*args)

iradinapy.iradinaFilePatterns.visualize_TDS_graphic (FILEDAT, ATTS, EXPR=[],
                                                    DIVIDE=None, FILS=[],
                                                    OPTS=[], Verbose=True)

    ATTS = ( ("x1:x2"), ("x3:x5") ) for example 2 Draws

iradinapy.iradinaFilePatterns.visualize_TDS_univariate (FILEDAT, ATTS,
                                                    EXPR=[], DIVIDE=None, FILS=[],
                                                    OPTS=[], Verbose=True)

```

iradinapy.iradinaGui module

This file is the main API file for iradinaGUI

Warning: NO ‘__main__’ call allowed,
Use ‘./iradinaGUI’ (in parent directory)

Usage: see file ./iradinaGUI


```

class iradinapy.iradinaGui.ArgumentParserNoExit (prog=None, usage=None, descrip-
tion=None, epilog=None, par-
ents=[], formatter_class=<class
'argparse.HelpFormatter'>,
prefix_chars='-', from-
file_prefix_chars=None,
argument_default=None,
conflict_handler='error',
add_help=True, al-
low_abbrev=True)

Bases: argparse.ArgumentParser

change Exiting method as no exit

exit (status=0, message=None)

filter_existing_file (string)

filter_float_positive (string)

filter_int_positive (string)

filter_list (string)
    parser filter from string 'xx,yy,zz,...' returns list (if not error with python exec(value=[xx,yy,zz,...]))

filter_list_float (string)
    parser filter from string 'xx,yy,zz,...' returns list (if not error with python exec(value=[xx,yy,zz,...]))

filter_list_int (string)
    parser filter from string 'xx,yy,zz,...' returns list (if not error with python exec(value=[xx,yy,zz,...]))

filter_logLevel (aStr)

filter_range (string)
    parser filter from string 'vmin,vmax' returns list (if not error with python exec(value=[xx,yy]))

filter_square (string)

filter_workdir (string)

getLogLevels ()

getLogLevelsStr ()

class iradinapy.iradinaGui.Ira (logger)
    Bases: object

    The main class that stores all the commands of iradinaGui (usually known as 'runner' argument in Command
    classes)

    assumeAsList (strOrList)

    execute_cli (cli_arguments)
        select first argument as a command in directory 'commands', and launch on arguments

        Parameters cli_arguments – (str or list) The iradinaGUI CLI arguments (as sys.argv)

    getAnswer (msg)
        question and user answer (in console) if confirm mode and not batch mode.

        returns 'YES' or 'NO' if confirm mode and not batch mode
        returns 'YES' if batch mode

    getBatchMode ()

    getColoredVersion ()
        get colored iradinaGui version message

```

```

getConfig ()
getConfirmMode ()
getId ()
    assimilated as integer incremented on _idCommandHandlers
getLogger ()
getOptions ()
get_help ()
    get general help colored string
parseArguments (arguments)
print_help ()
    prints iradinaGui general help
runGUI ()
    a main window for iradinaGUI
setConfirmMode (value)
show_doc ()
    show iradinaGui general documentation
iradinapy.iradinaGui.assumeAsList (strOrList)
    return a list as sys.argv if string
iradinapy.iradinaGui.cmdsdir = '/volatile2/wambeke/TULEAP_MATIX/MATIX_26-CO7/SOURCES/IRADINAGUI'
    if DBG.isDeveloper(): workdirdefault = os.path.realpath(os.path.join(rootdir, "..", "IRADINAGUI_WORKDIR"))
    else: workdirdefault = os.path.expandvars(os.path.join("$HOME", "IRADINAGUI_WORKDIR"))
iradinapy.iradinaGui.getVersion ()
    get version number as string
iradinapy.iradinaGui.launchIra (command)
    launch iradinaGUI as subprocess.Popen command as string ('iradinaGUI -help' for example) used for
    unittest, or else...

Returns RCO.ReturnCode

```

iradinapy.iradinaSettings module

```

class iradinapy.iradinaSettings.IradinaSettings
    Bases: settingspy.settings.Settings (page 72)

    may be future link to Qt QSettings for future do not forget window environment variables are NOT case
    sensitive user have to write environment variables as syntax ${...}

    policy: names setting variables beginning with "_" contains environment variables reference

iradinapy.iradinaSettings.checkAll ()
    used as singleton

iradinapy.iradinaSettings.checkEnvVar (val)
    used as singleton

iradinapy.iradinaSettings.getExpandedVar (name)
    used as singleton

iradinapy.iradinaSettings.getIradinaSysMacrosDir ()

iradinapy.iradinaSettings.getSettings ()
    used as singleton

```

```
iradinapy.iradinaSettings.getVar (name)
    used as singleton
iradinapy.iradinaSettings.setEnvVar (envVar, value)
iradinapy.iradinaSettings.setEnvVarByDefault (envVar, valueDefault)
```

iradinapy.loggingIra module

iradinaGui logger. using logging package

Define one logger with one handler on stdout and one handler on file for production.
Define another one logger for unittest.

see: <http://sametmax.com/ecrire-des-logs-en-python>

Define two LoggerIra instances in iradinaGui, no more need.

- `_loggerDefault` as production/development logger
- `_loggerUnittest` as unittest logger

see use of handlers of `_loggerDefault` for
log console and log files xml, txt

console handler:

- `info()` : no format
- `error()` `warning()` `trace()` `debug()` etc. :
 formatted indented on multi lines messages using handlers

file handlers:

- `info()` `error()` `warning()` `trace()` `debug()` etc. :
 formatted indented on multi lines messages using handlers

WARNING:

log step and log trace are present on stdout console or log file
following level handlers settings

```
class iradinapy.loggingIra.DefaultFormatter (fmt=None, datefmt=None, style='%')
```

Bases: `logging.Formatter`

format (record)

Format the specified record as text.

The record's attribute dictionary is used as the operand to a string formatting operation which yields the returned string. Before formatting the dictionary, a couple of preparatory steps are carried out. The message attribute of the record is computed using `LogRecord.getMessage()`. If the formatting string uses the time (as determined by a call to `usesTime()`, `formatTime()` is called to format the event time. If there is exception information, it is formatted using `formatException()` and appended to the message.

setColorLevelname (levelname)

set color implies color special characters and tabulate levelname length of string

```
class iradinapy.loggingIra.FileTxtFormatter (fmt=None, datefmt=None, style='%')
```

Bases: `logging.Formatter`

format (*record*)

Format the specified record as text.

The record's attribute dictionary is used as the operand to a string formatting operation which yields the returned string. Before formatting the dictionary, a couple of preparatory steps are carried out. The message attribute of the record is computed using `LogRecord.getMessage()`. If the formatting string uses the time (as determined by a call to `usesTime()`), `formatTime()` is called to format the event time. If there is exception information, it is formatted using `formatException()` and appended to the message.

class `iradinapy.loggingIra.FileXmlFormatter` (*fmt=None, datefmt=None, style='%'*)

Bases: `logging.Formatter`

format (*record*)

Format the specified record as text.

The record's attribute dictionary is used as the operand to a string formatting operation which yields the returned string. Before formatting the dictionary, a couple of preparatory steps are carried out. The message attribute of the record is computed using `LogRecord.getMessage()`. If the formatting string uses the time (as determined by a call to `usesTime()`), `formatTime()` is called to format the event time. If there is exception information, it is formatted using `formatException()` and appended to the message.

class `iradinapy.loggingIra.LoggerIra` (*name, level=20*)

Bases: `logging.Logger`

Inherited class `logging.Logger` for logger `iradinaGui`

add a level STEP as `log.step(msg)`

add a level TRACE as `log.trace(msg)`

below `log.info(msg)`

above `log.debug(msg)`

to assume message step inside files xml 'command's internal traces'

to assume store long log asci in files txt outside files xml

see: `/usr/lib64/python2.7/logging/__init__.py` etc.

close ()

final stuff for logger, done at end `iradinaGui` flushed and closed xml files have to be not overridden/appended

closeFileHandlerForCommand (*cmdInstance*)

getMainCommandHandler ()

returns handler for colored stdout console/terminal for human user eye `iradinaGUI` outputs

initLinkForCommand (*cmdParent, cmdNew*)

logStep (*step*)

current `logger.info()` step as 'header ... etc ...'

logStep_begin (*header, step=""*)

initialize for main handler (tty as stdout) a one line message for steps (... of compilation for example) as no return line message with `logger.info()` level

example:

'header ... first temporary step message ...'

'header ... etc ...' (on same line)

'header ... OK' (on same line)

logStep_end (*step, tab=None*)

last logger.info() step as 'header ... OK' or 'header ... KO'

setFileHandlerForCommand (*cmdParent, cmdInstance*)

add file handler to logger to set log files for a iradinaGui command. when command is known from pyconf/config instance

Example:

log files names for command prepare

with micro commands clean/source/patch

~/LOGS/20180510_140606_prepare_lenovo.xml

~/LOGS/OUT/20180510_140606_prepare_lenovo.txt

~/LOGS/micro_20180510_140607_clean_lenovo.xml

~/LOGS/OUT/micro_20180510_140607_clean_lenovo.txt

etc.

setLevelMainHandler (*level*)

step (*msg, *args, **kwargs*)

Log 'msg % args' with severity '_STEP'.

testNoReturn ()

test when message ending '...' and level info then no return mode

trace (*msg, *args, **kwargs*)

Log 'msg % args' with severity '_TRACE'.

xx_isEnabledFor (*level*)

Is this logger enabled for level 'level'? currently not modified from logging.Logger class, here only for call log debug.

class iradinapy.loggingIra.**StreamHandlerIra** (*stream=None*)

Bases: logging.StreamHandler

A handler class which writes logging records, appropriately formatted, to a stream. Note that this class does not close the stream, as sys.stdout or sys.stderr may be used.

from logging.StreamHandler class, modified for 'no return' mode line if '...' at end of record message

emit (*record*)

Emit a record.

If a formatter is specified, it is used to format the record. The record is then written to the stream with a trailing newline. If exception information is present, it is formatted using traceback.print_exception and appended to the stream. If the stream has an 'encoding' attribute, it is used to determine how to do the output to the stream.

isLastRecordHaveNoReturn ()

to memorize if last info record is 'no return' mode (as ending '...') avoid define inherited __init__

isNeedFirstReturn (*record*)

'no return' mode valid only if 2 consecutives info messages if not, needs insert return line BEFORE (warning, debug, or other) current record message

class iradinapy.loggingIra.**UnittestFormatter** (*fmt=None, datefmt=None, style='%')*

Bases: logging.Formatter

format (*record*)

Format the specified record as text.

The record's attribute dictionary is used as the operand to a string formatting operation which yields the returned string. Before formatting the dictionary, a couple of preparatory steps are carried out. The

message attribute of the record is computed using `LogRecord.getMessage()`. If the formatting string uses the time (as determined by a call to `usesTime()`), `formatTime()` is called to format the event time. If there is exception information, it is formatted using `formatException()` and appended to the message.

class `iradinapy.loggingIra.UnittestStream`

Bases: `object`

write my stream class only write and flush are used for the streaming

<https://docs.python.org/2/library/logging.handlers.html>

<https://stackoverflow.com/questions/31999627/storing-logger-messages-in-a-string>

flush ()

getLogs ()

getLogsAndClear ()

write (*astr*)

final method called when message is logged

class `iradinapy.loggingIra.XmlHandler` (*capacity*)

Bases: `logging.handlers.BufferingHandler`

log outputs in memory as `BufferingHandler`. Write `ElementTree` in file and flush are done once when method `close` is called, to generate xml file.

`atts = {`

 "fileName": xml file name of micro command

 "command": cmd, # 'compile' or 'prepare' etc.

 "passed": res, # 'O' or 'I'

 "launchedCommand": fullcmd, # 'compile TOTO -etc'

`}`

see: <https://docs.python.org/2/library/logging.handlers.html>

close ()

prepare `ElementTree` from existing logs and write xml file

warning: avoid iradinaGUI logging message in logger close phase

createLogField ()

prepare formatted string from self.buffer `LogRecord` for xml 'Log' node using handler formatter

createLogFieldFromScrath ()

prepare formatted string from self.buffer `LogRecord` for xml 'Log' node local format

set_config (*config*)

config is supposedly non existing, no overwrite accepted

set_target_file (*filename*)

filename is file name xml with path supposedly non existing, no overwrite accepted

`iradinapy.loggingIra.filterLevel` (*aLevel*)

filter levels logging values from firsts characters levels. No case sensitive.

example:

'i' -> 'INFO'

‘cRiT’ -> ‘CRITICAL’

```

iradinapy.loggingIra.getCurrentLogger()
    get one of _loggerDefault or _loggerUnittest as first created by getDefaultLogger() or getUnittestLogger():

iradinapy.loggingIra.getDefaultLogger()
    official method to get the only one instance of Default Logger

iradinapy.loggingIra.getListOfStrLogRecord (listOfLogRecord)
    Returns one line string for logging LogRecord description

iradinapy.loggingIra.getLogger()

iradinapy.loggingIra.getMessage (self)
    modified from logging.__init__.LogRecord.getMessage, better message on format error Return the message
    for this LogRecord.

    Return the message for this LogRecord after merging any user-supplied arguments with the message.

iradinapy.loggingIra.getStrDirLogger (logger)
    Returns multi line string for logger description, with dir(logger). Used for debug

iradinapy.loggingIra.getStrHandler (handler)
    Returns one line string for handler description (as inexisting __repr__) to avoid create inherited classe(s)
    handler

iradinapy.loggingIra.getStrLogRecord (logRecord)
    Returns one line string for simple logging LogRecord description

iradinapy.loggingIra.getStrShort (msg)
    Returns short string for msg (as first characters without line feed

iradinapy.loggingIra.getUnittestLogger()
    official method to get the only one instance of Unittest Logger

iradinapy.loggingIra.indent (msg, nb, car=' ')
    indent nb car (spaces) multi lines message except first one

iradinapy.loggingIra.indentUnittest (msg, prefix='| ')
    indent multi lines message except first one with prefix. prefix default is designed for less spaces for size
    logs files and keep logs human eye readable

iradinapy.loggingIra.initLoggerAsDefault (logger, fmt=None, level=None)
    init logger as prefixed message and indented message if multi line except info() outed ‘as it’ without any
    format. level could be modified during execution

iradinapy.loggingIra.initLoggerAsUnittest (logger, fmt=None, level=None)
    init logger as silent on stdout/stderr used for retrieve messages in memory for post execution unittest https://docs.python.org/2/library/logging.handlers.html

iradinapy.loggingIra.log (msg, force=False)
    elementary log when no logging.Logger yet

iradinapy.loggingIra.testLogger_1 (logger)
    small test

iradinapy.loggingIra.testMain()

iradinapy.loggingIra.testNoReturn (logger)
    test when message ending ‘...’ and level info then no return mode

```

iradinapy.mainWindowIra module

iradinapy.modelIra module

```
class iradinapy.modelIra.ModelIra
    Bases: xyzpy.baseXyz._XyzConstrainBase
    general instance to group all iradina data files in a directory input file iradina release ?

    getActionsContextMenu ()
    getEtudeWorkdirBrut (expanded=True)
    getEtudeWorkdirExpanded ()
    getHistoryFile ()
    isHidden (nameAttr)
        to know if attribute is currently displayed in treeView and other dialog widget
    setDefaultValues ()
        not virtual, could be used
    setFromFileIra (fileName, verbose=False)
        override inherited method
    toStrIra ()
        override inherited method
    userExpand ()
        filename patterns ‘,??’ warning not for ‘[ ‘]’ as ‘alist[]’ no found way to quote meta-character
        https://docs.python.org/2/library/fnmatch.html
    userMode ()
        change user mode
```

iradinapy.testPrerequisitesIra module

```
iradinapy.testPrerequisitesIra.TestImports ()
    test of prerequisites import python for IradinaGui message for problem(s), aborting immediatly.

iradinapy.testPrerequisitesIra.TestIradinaFeatures ()
    test of iradina CODE features

iradinapy.testPrerequisitesIra.error (message)
```

iradinapy.treeViewIra module

```
iradinapy.treeViewIra.verboseEvent = False
    cosmetic stuff for treeView Iradina
```


iradinapy.utilsIra module

utilities for iradinaGUI general useful simple methods all-in-one import iradinapy.utilsIra as UTS

Usage:

```
>> import iradinapy.utilsIra as UTS
```

```
>> UTS.ensure_path_exists(path)
```

```
iradinapy.utilsIra.Popen (command, shell=True, cwd=None, env=None, stdout=- 1, stderr=- 1,  
                           logger=None)  
    make subprocess.Popen(cmd), with call logger.trace and logger.error if problem as returncode != 0
```

```
iradinapy.utilsIra.addSpaces (idx, aStr)
```

```
iradinapy.utilsIra.black (msg)
```

```
iradinapy.utilsIra.blue (msg)
```

```
iradinapy.utilsIra.critical (msg)
```

```
iradinapy.utilsIra.cyan (msg)
```

```
iradinapy.utilsIra.deepcopy_list (input_list)  
    Do a deep copy of a list
```

Parameters **input_list** – (list) The list to copy

Returns (list) The copy of the list

```
iradinapy.utilsIra.ensure_file_exists (aFile, aDefaultFile)  
    Create a file if not existing, copying from default file
```

Parameters

- **aFilePath** – (str) The file to ensure existence
- **aDefaultFile** – (str) The default file to copy if not existing

```
iradinapy.utilsIra.ensure_path_exists (path)  
    Create a path if not existing
```

Parameters **path** – (str) The path.

```
iradinapy.utilsIra.error (msg)
```

```
iradinapy.utilsIra.formatTuples (tuples)  
    Format 'label = value' the tuples in a tabulated way.
```

Parameters **tuples** – (list) The list of tuples to format

Returns (str) The tabulated text. (as multiples lines)

```
iradinapy.utilsIra.formatValue (label, value, suffix="")  
    format 'label = value' with the info color
```

Parameters

- **label** – (int) the label to print.
- **value** – (str) the value to print.
- **suffix** – (str) the optionnal suffix to add at the end.

```
iradinapy.utilsIra.get_iradinaGUI_version (config)
```

```
iradinapy.utilsIra.get_tmp_filename (config, name)
```

```
iradinapy.utilsIra.green (msg)
```

`iradinapy.utilsIra.header (msg)`

`iradinapy.utilsIra.info (msg)`

`iradinapy.utilsIra.label (msg)`

`iradinapy.utilsIra.magenta (msg)`

`iradinapy.utilsIra.merge_dicts (*dict_args)`

Given any number of dicts, shallow copy and merge into a new dict, precedence goes to key value pairs in latter dicts.

`iradinapy.utilsIra.normal (msg)`

`iradinapy.utilsIra.red (msg)`

`iradinapy.utilsIra.remove_item_from_list (input_list, item)`

Remove all occurrences of item from input_list

Parameters `input_list` – (list) The list to modify

Returns (list) The without any item

`iradinapy.utilsIra.replace_in_file (file_in, str_in, str_out)`

Replace <str_in> by <str_out> in file <file_in>. save a file old version as file_in + ‘_old’

Parameters

- **file_in** – (str) The file name
- **str_in** – (str) The string to search
- **str_out** – (str) The string to replace.

`iradinapy.utilsIra.reset (msg)`

`iradinapy.utilsIra.sleep (sec)`

`iradinapy.utilsIra.success (msg)`

`iradinapy.utilsIra.tabColor (*args)`

return tabulated colored string from args, assume true length of color tags as <OK> <info> etc. to correct alignment when tags are interpreted as (no-length-spacing) color for colorama use or else

`iradinapy.utilsIra.warning (msg)`

`iradinapy.utilsIra.white (msg)`

`iradinapy.utilsIra.yellow (msg)`

Module contents

4.1.2 configparserpy

configparserpy package

Subpackages

configparserpy.test package

Submodules

configparserpy.test.test_130_configParserUtils module

utilities for best use ConfigParser

see:

<https://wiki.python.org/moin/ConfigParserExamples>

<https://docs.python.org/2/library/configparser.html>

```
class configparserpy.test.test_130_configParserUtils.TestCase (methodName='runTest')
    Bases: unittest.case.TestCase
    Test the configParserUtils.py

    test_000 ()
    test_010 ()
    test_020 ()
    test_030 ()
    test_032 ()
    test_034 ()
    test_100 ()
    test_999 ()
```

Module contents

Submodules

configparserpy.configParserUtils module

utilities for best use ConfigParser

see: <https://wiki.python.org/moin/ConfigParserExamples>

```
class configparserpy.configParserUtils.UtSafeConfigParser (*args, **kwargs)
    Bases: configparser.SafeConfigParser

    SafeConfigParser with ExtendedInterpolation, and __repr__, and readDefaultAndUser to merge default and
    user config

    copy ()
    isEmpty ()
    readDefaultAndUser (aStrDefault, aStrUser)
        merge user overriding origin defaults
    readFromStr (aStr, merge=False)
        allow merge only explicitly
    toCatchAll (verbose=False)
        permits class attribute writings, (but raise on accentuation and avoid spaces in section names)

    cfg = UtSafeConfigParser()
    cfg.readFromStr(""" | [General]
reporter = tintin
""")
    config = cfg.toCatchAll()
    print(config.General.reporter) # -> "tintin"
```

```

toDict (verbose=False)
toDictTuple (verbose=False)
toOrderedDict (verbose=False)
writeToStr ()
    allow merge only explicitly
configparserpy.configParserUtils.getConfigFromDefaultAndUserStr (aStrDefault,
                                                                    aStrUser)
    simple create config from Default an overrides from User as strings
configparserpy.configParserUtils.getConfigFromFile (aFile)
configparserpy.configParserUtils.getConfigFromStr (aStr)
    simple create config from contents as string

```

Module contents

4.1.3 settingspy

settingspy package

Submodules

settingspy.setStyleFactory module

```
settingspy.setStyleFactory.run()
```

settingspy.settings module

```
class settingspy.settings.Settings
```

Bases: object

may be future link to Qt QSettings for future do not forget window environment variables are NOT case sensitive user have to write environment variables as syntax `${...}`

policy: names setting variables beginning with “_” contains environment variables reference

```
checkAll ()
```

expand var in settings return (ok, aDict) ok is False or True aDict is settings as aDict[key] = (value, interpretedValue)

```
checkEnvVar (aStrWithEnvVar)
```

check all env vars contained as syntax `${...}` defined in environ

```
getExpandedVar (name)
```

returns expanded value of var name, or None if inexistent or problem in expand

```
getRealPath (aPathWithEnvVar)
```

resolve file path env variable as `${HOME}/toto` etc... with `os.path.expandvars` interpretation of env var

```
getVar (name, Verbose=True)
```

return NOT expanded value of var name

```
setVar (name, value, Verbose=True)
```

no control, user choice with `checkAll()`

```
settingspy.settings.getExpandedVar (name)
```

used as singleton

```
settingspy.settings.getSettings()
    used as singleton

settingspy.settings.getVar(name)
    used as singleton

settingspy.settings.setEnvVar(envVar, value)
    with message warning if change

settingspy.settings.setEnvVarByDefault(envVar, valueDefault)
    only for single environ variables: envVar='HOME' for ${HOME} or $HOME valueDefault have to be
    expanded (i.e. without '$')
```

Module contents

settingspy for salome matix

4.1.4 filewatcherpy

filewatcherpy package

Subpackages

filewatcherpy.test package

Submodules

filewatcherpy.test.test_340_fileWatcher module

```
class filewatcherpy.test.test_340_fileWatcher.TestCase(methodName='runTest')
    Bases: unittest.case.TestCase

    test_010()

    test_020()

    test_030()

    test_999()
```

Module contents

Submodules

filewatcherpy.fileWatcher module

```
filewatcherpy.fileWatcher.exampleLaunchStandalone()

filewatcherpy.fileWatcher.getFileWatcher()
    use it as singleton

filewatcherpy.fileWatcher.getRealPath(aPathWithEnvVar)
    resolve env variable as $HOME/toto etc... with expandvars

filewatcherpy.fileWatcher.getRealPath_obsolete(aPathWithEnvVar)
    resolve env variable as $HOME/toto etc... with subprocess shell interpretation of env var
```

Module contents

filewatcher.py for salome matix

RELEASE NOTES

5.1 Release notes

In construction.

PYTHON MODULE INDEX

C

configparserpy, 72
configparserpy.configParserUtils, 71
configparserpy.test, 71
configparserpy.test.test_130_configParserUtils,
70

f

filewatcherpy, 74
filewatcherpy.fileWatcher, 73
filewatcherpy.test, 73
filewatcherpy.test.test_340_fileWatcher,
73

i

iradinapy, 70
iradinapy.abcdExpression, 45
iradinapy.analysisIra, 45
iradinapy.caseIradina, 49
iradinapy.colorama, 43
iradinapy.colorama.ansi, 40
iradinapy.colorama.ansitowin32, 41
iradinapy.colorama.initialise, 42
iradinapy.colorama.win32, 42
iradinapy.colorama.winterm, 43
iradinapy.coloringIra, 55
iradinapy.configIra, 56
iradinapy.controllerIra, 57
iradinapy.controlSimulationIra, 56
iradinapy.dateTime, 57
iradinapy.example, 45
iradinapy.example.essai_logging_1, 43
iradinapy.example.essai_logging_2, 44
iradinapy.iradinaFilePatterns, 59
iradinapy.iradinaGui, 60
iradinapy.iradinaSettings, 62
iradinapy.loggingIra, 63
iradinapy.mainWindowIra, 68
iradinapy.modelIra, 68
iradinapy.testPrerequisitesIra, 68
iradinapy.treeViewIra, 68
iradinapy.utilsIra, 69

S

settingspy, 73
settingspy.setStyleFactory, 72
settingspy.settings, 72

A

addItem() (*iradinapy.analysisIra.ListOfFileViewerXyz* method), 47

addItem() (*iradinapy.analysisIra.ListOfFileViewerXyz* method), 47

addItemSlot() (*iradinapy.analysisIra.ListOfFileViewerXyz* method), 47

addSeconds() (*iradinapy.dateTime.DateTime* method), 57

addSpaces() (*in module iradinapy.utilsIra*), 69

AnalysisIra (*class in iradinapy.analysisIra*), 45

ANSI_CSI_RE (*iradinapy.colorama.ansitowin32.AnsiToWin32* attribute), 41

ANSI_OSC_RE (*iradinapy.colorama.ansitowin32.AnsiToWin32* attribute), 41

AnsiBack (*class in iradinapy.colorama.ansi*), 40

AnsiCodes (*class in iradinapy.colorama.ansi*), 40

AnsiCursor (*class in iradinapy.colorama.ansi*), 40

AnsiFore (*class in iradinapy.colorama.ansi*), 41

AnsiStyle (*class in iradinapy.colorama.ansi*), 41

AnsiToWin32 (*class in iradinapy.colorama.ansitowin32*), 41

appendHistoryAction() (*iradinapy.analysisIra.HistoryFileManagerXyz* method), 47

appendHistoryCopyOf() (*iradinapy.analysisIra.HistoryFileManagerXyz* method), 47

appendHistoryFileManager() (*iradinapy.analysisIra.AnalysisIra* method), 45

ArgumentParserNoExit (*class in iradinapy.iradinaGui*), 60

assertUserDefaultFiles() (*iradinapy.configIra.ConfigManager* method), 56

assumeAsList() (*in module iradinapy.iradinaGui*), 62

assumeAsList() (*iradinapy.iradinaGui.Ira* method), 61

AttributeDataFrameIra (*class in iradinapy.analysisIra*), 45

B

BACK() (*iradinapy.colorama.ansi.AnsiCursor* method), 40

back() (*iradinapy.colorama.winterm.WinTerm* method), 43

BeamSpreadIra (*class in iradinapy.caseIradina*), 49

BLACK (*iradinapy.colorama.ansi.AnsiBack* attribute), 40

BLACK (*iradinapy.colorama.ansi.AnsiFore* attribute), 41

BLACK (*iradinapy.colorama.winterm.WinColor* attribute), 43

black() (*in module iradinapy.utilsIra*), 69

BLUE (*iradinapy.colorama.ansi.AnsiBack* attribute), 40

BLUE (*iradinapy.colorama.ansi.AnsiFore* attribute), 41

BLUE (*iradinapy.colorama.winterm.WinColor* attribute), 43

blue() (*in module iradinapy.utilsIra*), 69

BoolFalseIra (*class in iradinapy.caseIradina*), 49

BoolTrueIra (*class in iradinapy.caseIradina*), 49

BRIGHT (*iradinapy.colorama.ansi.AnsiStyle* attribute), 41

BRIGHT (*iradinapy.colorama.winterm.WinStyle* attribute), 43

BRIGHT_BACKGROUND (*iradinapy.colorama.winterm.WinStyle* attribute), 43

browseElement() (*iradinapy.caseIradina.IsotopeIra* method), 52

browseElement() (*iradinapy.caseIradina.TargetComponentIra* method), 54

browseViewerDialog() (*iradinapy.analysisIra.ListOfFileViewerXyz* method), 47

browseViewerExecOnApply() (*iradinapy.analysisIra.ListOfFileViewerXyz* method), 47

C

call_win32() (*iradinapy.colorama.ansitowin32.AnsiToWin32* method), 41

CaseIra (*class in iradinapy.caseIradina*), 49

CellCountxIra (*class in iradinapy.caseIradina*), 49

- CellCountyIra (class in iradinapy.caseIradina), 49
- CellCountzIra (class in iradinapy.caseIradina), 49
- CellDepthxIra (class in iradinapy.caseIradina), 49
- CellMultiLayerxIra (class in iradinapy.caseIradina), 50
- CellSizeIxIra (class in iradinapy.caseIradina), 50
- CellSizeyIra (class in iradinapy.caseIradina), 50
- CellSizezIra (class in iradinapy.caseIradina), 50
- checkAll() (in module iradinapy.iradinaSettings), 62
- checkAll() (settingspy.settings.Settings method), 72
- checkEnvVar() (in module iradinapy.iradinaSettings), 62
- checkEnvVar() (settingspy.settings.Settings method), 72
- checkFileExist() (iradinapy.configIra.ConfigManager method), 56
- checkValues() (iradinapy.caseIradina.IsotopeIra method), 52
- checkValues() (iradinapy.caseIradina.TargetComponentIra method), 54
- cleanColors() (in module iradinapy.coloringIra), 55
- clear_line() (in module iradinapy.colorama.ansi), 41
- clear_screen() (in module iradinapy.colorama.ansi), 41
- clearHistory() (iradinapy.analysisIra.HistoryFileManagerXyz method), 47
- close() (iradinapy.loggingIra.LoggerIra method), 64
- close() (iradinapy.loggingIra.XmlHandler method), 66
- closeFileHandlerForCommand() (iradinapy.loggingIra.LoggerIra method), 64
- cmdsdir (in module iradinapy.iradinaGui), 62
- code_to_chars() (in module iradinapy.colorama.ansi), 41
- colorama_text() (in module iradinapy.colorama.initialise), 42
- ColoringStream (class in iradinapy.coloringIra), 55
- CompositionFileTypeIra (class in iradinapy.caseIradina), 50
- ConcentrationIra (class in iradinapy.caseIradina), 50
- ConfigManager (class in iradinapy.configIra), 56
- configparserpy module, 72
- configparserpy.configParserUtils module, 71
- configparserpy.test module, 71
- configparserpy.test.test_130_configParserUtils module, 70
- ControlSimulationIra (class in iradinapy.controlSimulationIra), 56
- convert_ansi() (iradinapy.colorama.ansitowin32.AnsiToWin32 method), 41
- convert_osc() (iradinapy.colorama.ansitowin32.AnsiToWin32 method), 42
- copy() (configparserpy.configParserUtils.UtSafeConfigParser method), 71
- copyAllFileInData() (iradinapy.analysisIra.DataManagerIra method), 46
- copyFileInData() (iradinapy.analysisIra.DataIra method), 46
- createDocLaunch() (iradinapy.analysisIra.AnalysisIra method), 45
- createEditorData() (iradinapy.analysisIra.ExpressionIra method), 46
- createLogField() (iradinapy.loggingIra.XmlHandler method), 66
- createLogFieldFromScrath() (iradinapy.loggingIra.XmlHandler method), 66
- critical() (in module iradinapy.utilsIra), 69
- cursor_adjust() (iradinapy.colorama.winterm.WinTerm method), 43
- CYAN (iradinapy.colorama.ansi.AnsiBack attribute), 40
- CYAN (iradinapy.colorama.ansi.AnsiFore attribute), 41
- CYAN (iradinapy.colorama.winterm.WinColor attribute), 43
- cyan() (in module iradinapy.utilsIra), 69
- ## D
- DataInformationsIra (class in iradinapy.analysisIra), 46
- DataIra (class in iradinapy.analysisIra), 46
- DataManagerIra (class in iradinapy.analysisIra), 46
- date_to_datetime() (in module iradinapy.dateTime), 59
- DateTime (class in iradinapy.dateTime), 57
- deepcopy_list() (in module iradinapy.utilsIra), 69
- DefaultFormatter (class in iradinapy.loggingIra), 63
- deinit() (in module iradinapy.colorama.initialise), 42
- DeltaTime (class in iradinapy.dateTime), 58
- DensityIra (class in iradinapy.caseIradina), 50
- DensityTargetComponentIra (class in iradinapy.caseIradina), 51
- DEINIT (iradinapy.colorama.ansi.AnsiStyle attribute), 41

DisplayIntervalIra (class in iradinapy.caseIradina), 51
 DOWN() (iradinapy.colorama.ansi.AnsiCursor method), 40
 drawDialogDataServer() (iradinapy.analysisIra.DataIra method), 46
 drawGraphic() (in module iradinapy.analysisIra), 48
 drawGraphic() (iradinapy.analysisIra.AttributeDataFrameIra method), 45
 drawGraphic() (iradinapy.analysisIra.ExpressionIra method), 46
 drawUnivariate() (in module iradinapy.analysisIra), 48
 drawUnivariate() (iradinapy.analysisIra.AttributeDataFrameIra method), 45
 drawUnivariate() (iradinapy.analysisIra.ExpressionIra method), 46

E

ElementCountIra (class in iradinapy.caseIradina), 51
 ElementReplEnergyIra (class in iradinapy.caseIradina), 51
 emit() (iradinapy.loggingIra.StreamHandlerIra method), 65
 ensure_file_exists() (in module iradinapy.utilsIra), 69
 ensure_path_exists() (in module iradinapy.utilsIra), 69
 erase_line() (iradinapy.colorama.winterm.WinTerm method), 43
 erase_screen() (iradinapy.colorama.winterm.WinTerm method), 43
 error() (in module iradinapy.testPrerequisitesIra), 68
 error() (in module iradinapy.utilsIra), 69
 exampleLaunchStandalone() (in module filewatcherpy.fileWatcher), 73
 execReplaces() (in module iradinapy.iradinaFilePatterns), 59
 execute_cli() (iradinapy.iradinaGui.Ira method), 61
 exit() (iradinapy.iradinaGui.ArgumentParserNoExit method), 61
 ExpressionIra (class in iradinapy.analysisIra), 46
 extract_params() (iradinapy.colorama.ansitowin32.AnsiToWin32 method), 42

F

FileIra (class in iradinapy.analysisIra), 47
 FileTxtFormatter (class in iradinapy.loggingIra), 63
 filewatcherpy module, 74
 filewatcherpy.fileWatcher module, 73
 filewatcherpy.test module, 73
 filewatcherpy.test.test_340_fileWatcher module, 73
 FileXmlFormatter (class in iradinapy.loggingIra), 64
 filter_existing_file() (iradinapy.iradinaGui.ArgumentParserNoExit method), 61
 filter_float_positive() (iradinapy.iradinaGui.ArgumentParserNoExit method), 61
 filter_int_positive() (iradinapy.iradinaGui.ArgumentParserNoExit method), 61
 filter_list() (iradinapy.iradinaGui.ArgumentParserNoExit method), 61
 filter_list_float() (iradinapy.iradinaGui.ArgumentParserNoExit method), 61
 filter_list_int() (iradinapy.iradinaGui.ArgumentParserNoExit method), 61
 filter_logLevel() (iradinapy.iradinaGui.ArgumentParserNoExit method), 61
 filter_range() (iradinapy.iradinaGui.ArgumentParserNoExit method), 61
 filter_square() (iradinapy.iradinaGui.ArgumentParserNoExit method), 61
 filter_workdir() (iradinapy.iradinaGui.ArgumentParserNoExit method), 61
 filterColumnsNamesForUranie() (in module iradinapy.iradinaFilePatterns), 59
 filterHeaderDat() (in module iradinapy.iradinaFilePatterns), 59
 filterLevel() (in module iradinapy.loggingIra), 66
 FlightLengthTypeIra (class in iradinapy.caseIradina), 51
 FloatListIra (class in iradinapy.caseIradina), 51
 flush() (iradinapy.coloringIra.ColoringStream method), 55
 flush() (iradinapy.loggingIra.UnittestStream method), 66
 fn_heterogenous_random_multiple_materials() (in module iradinapy.analysisIra), 48
 fn_homogenous_one_material() (in module

iradinapy.analysisIra), 48

`fn_multiLayer_multiple_materials()` (in module *iradinapy.analysisIra*), 48

`fore()` (*iradinapy.colorama.winterm.WinTerm* method), 43

`format()` (*iradinapy.example.essai_logging_2.MyFormatter* method), 44

`format()` (*iradinapy.loggingIra.DefaultFormatter* method), 63

`format()` (*iradinapy.loggingIra.FileTxtFormatter* method), 63

`format()` (*iradinapy.loggingIra.FileXmlFormatter* method), 64

`format()` (*iradinapy.loggingIra.UnittestFormatter* method), 65

`FORMAT_DATE_CONFIG` (*iradinapy.dateTime.DateTime* attribute), 57

`FORMAT_DATEHOUR_CONFIG` (*iradinapy.dateTime.DateTime* attribute), 57

`FORMAT_FILE` (*iradinapy.dateTime.DateTime* attribute), 57

`FORMAT_HOUR_CONFIG` (*iradinapy.dateTime.DateTime* attribute), 57

`FORMAT_HUMAN` (*iradinapy.dateTime.DateTime* attribute), 57

`FORMAT_PACKAGE` (*iradinapy.dateTime.DateTime* attribute), 57

`FORMAT_XML` (*iradinapy.dateTime.DateTime* attribute), 57

`formatTuples()` (in module *iradinapy.utilsIra*), 69

`formatValue()` (in module *iradinapy.utilsIra*), 69

`FORWARD()` (*iradinapy.colorama.ansi.AnsiCursor* method), 40

`fromDateHourConfig()` (in module *iradinapy.dateTime*), 59

`fromTimeStamp()` (in module *iradinapy.dateTime*), 59

`FunctionIra` (class in *iradinapy.analysisIra*), 47

G

`get_attrs()` (*iradinapy.colorama.winterm.WinTerm* method), 43

`get_cell_count_x()` (*iradinapy.caseIradina.StructureIra* method), 54

`get_help()` (*iradinapy.iradinaGui.Ira* method), 62

`get_iradinaGUI_version()` (in module *iradinapy.utilsIra*), 69

`get_position()` (*iradinapy.colorama.winterm.WinTerm* method), 43

`get_tmp_filename()` (in module *iradinapy.utilsIra*), 69

`get_value_random_multiple_materials()` (in module *iradinapy.analysisIra*), 49

`get_win32_calls()` (*iradinapy.colorama.ansitowin32.AnsiToWin32* method), 42

`getActionsContextMenu()` (*iradinapy.analysisIra.AnalysisIra* method), 45

`getActionsContextMenu()` (*iradinapy.analysisIra.AttributeDataFrameIra* method), 45

`getActionsContextMenu()` (*iradinapy.analysisIra.DataIra* method), 46

`getActionsContextMenu()` (*iradinapy.analysisIra.DataManagerIra* method), 46

`getActionsContextMenu()` (*iradinapy.analysisIra.ExpressionIra* method), 46

`getActionsContextMenu()` (*iradinapy.analysisIra.ListOfFileViewerXyz* method), 47

`getActionsContextMenu()` (*iradinapy.caseIradina.DensityIra* method), 50

`getActionsContextMenu()` (*iradinapy.caseIradina.DensityTargetComponentIra* method), 51

`getActionsContextMenu()` (*iradinapy.caseIradina.IsotopeIra* method), 52

`getActionsContextMenu()` (*iradinapy.caseIradina.TargetComponentIra* method), 54

`getActionsContextMenu()` (*iradinapy.modelIra.ModelIra* method), 68

`getAllAttributesName()` (*iradinapy.analysisIra.DataIra* method), 46

`getAllAttributesName()` (*iradinapy.analysisIra.ListOfAttributeIra* method), 47

`getAllAttributesName()` (*iradinapy.analysisIra.ListOfExpressionIra* method), 47

`getAllAttributesName()` (*iradinapy.caseIradina.ListOfMaterialIra* method), 52

`getAllAttributesNameInParents()` (*iradinapy.analysisIra.ExpressionIra* method), 46

`getAnswer()` (*iradinapy.iradinaGui.Ira* method), 61

`getAttributeName()` (*iradinapy.analysisIra.AttributeDataFrameIra* method), 45

`getAttributeName()` (*iradinapy.analysisIra.ExpressionIra* method), 46

`getBaseFiles()` (in module *iradinapy.iradinaFilePatterns*), 59

`getBatchMode()` (*iradinapy.iradinaGui.Ira* method), 61

`getCalculatedValue()` (*iradi-*

napy.caseIradina.DensityIra method), 50

getCellSizeX() (*iradina.napy.caseIradina.StructureIra* method), 54

getColoredVersion() (*iradina.napy.iradinaGui.Ira* method), 61

getCompleteFileName() (*iradina.napy.analysisIra.HistoryFileManagerXyz* method), 47

getConfig() (*iradina.napy.iradinaGui.Ira* method), 62

getConfigFromDefaultAndUserStr() (in module *configparser.py.configParserUtils*), 72

getConfigFromFile() (in module *configparser.py.configParserUtils*), 72

getConfigFromStr() (in module *configparser.py.configParserUtils*), 72

getConfirmMode() (*iradina.napy.iradinaGui.Ira* method), 62

getCount() (*iradina.napy.caseIradina.CellMultiLayerxIra* method), 50

getCurrentLogger() (in module *iradina.napy.loggingIra*), 67

getCurrentMode() (in module *iradina.napy.configIra*), 56

getCurrentRowColumn() (in module *iradina.napy.analysisIra*), 48

getDefaultConfig() (*iradina.napy.configIra.ConfigManager* method), 56

getDefaultDivide() (in module *iradina.napy.iradinaFilePatterns*), 59

getDefaultLogger() (in module *iradina.napy.loggingIra*), 67

getDefaultRowColumn() (in module *iradina.napy.analysisIra*), 48

getDirectory() (*iradina.napy.analysisIra.ListOfFileViewerXyz* method), 48

getDirectory() (*iradina.napy.analysisIra.ListOfUserFileIra* method), 48

getElementCount() (*iradina.napy.caseIradina.MaterialIra* method), 53

getElementsConc() (*iradina.napy.caseIradina.MaterialIra* method), 53

getElementsDispEnergy() (*iradina.napy.caseIradina.MaterialIra* method), 53

getElementsLattEnergy() (*iradina.napy.caseIradina.MaterialIra* method), 53

getElementsM() (*iradina.napy.caseIradina.MaterialIra* method), 53

getElementsReplEnergy() (*iradina.napy.caseIradina.MaterialIra* method), 53

getElementsSurfEnergy() (*iradina.napy.caseIradina.MaterialIra* method), 53

getElementsSymbol() (*iradina.napy.caseIradina.MaterialIra* method), 53

getElementsZ() (*iradina.napy.caseIradina.MaterialIra* method), 53

getEtudeWorkdir() (*iradina.napy.analysisIra.DataInformationsIra* method), 46

getEtudeWorkdirBrut() (*iradina.napy.analysisIra.DataInformationsIra* method), 46

getEtudeWorkdirBrut() (*iradina.napy.modelIra.ModelIra* method), 68

getEtudeWorkdirExpanded() (*iradina.napy.modelIra.ModelIra* method), 68

getExistingModes() (in module *iradina.napy.configIra*), 56

getExpandedVar() (in module *iradina.napy.iradinaSettings*), 62

getExpandedVar() (in module *settingspy.settings*), 72

getExpandedVar() (*settingspy.settings.Settings* method), 72

getExpressions() (*iradina.napy.analysisIra.ListOfExpressionIra* method), 47

getExpressionsInParent() (*iradina.napy.analysisIra.AttributeDataFrameIra* method), 45

getExpressionsInParent() (*iradina.napy.analysisIra.ExpressionIra* method), 46

getFileHash() (*iradina.napy.analysisIra.HistoryFileManagerXyz* method), 47

getFileInParent() (*iradina.napy.analysisIra.AttributeDataFrameIra* method), 46

getFileInParent() (*iradina.napy.analysisIra.ExpressionIra* method), 46

getFilePatterns() (in module *iradina.napy.iradinaFilePatterns*), 59

getFileWatcher() (in module *filewatcher.py.fileWatcher*), 73

getFixedUsefulDirs() (in module *iradina.napy.iradinaFilePatterns*), 59

getHeaderContentsFileDat() (in module *iradina.napy.iradinaFilePatterns*), 59

getHeaderFileDat() (in module *iradi-*

napy.iradinaFilePatterns), 60

`getHistoryFile()` (*iradinapy.modelIra.ModelIra method*), 68

`getId()` (*iradinapy.iradinaGui.Ira method*), 62

`getIdentFile()` (*iradinapy.analysisIra.HistoryFileManagerXyz method*), 47

`getIgnoreFilesForCpack()` (*in module iradinapy.iradinaFilePatterns*), 60

`getIndiceFromChar()` (*in module iradinapy.abcdExpression*), 45

`getIndiceFromChar()` (*iradinapy.caseIradina.CellMultiLayerxIra method*), 50

`getIradinaSysMacrosDir()` (*in module iradinapy.iradinaSettings*), 62

`getListOfStrLogRecord()` (*in module iradinapy.loggingIra*), 67

`getLogger()` (*in module iradinapy.loggingIra*), 67

`getLogger()` (*iradinapy.iradinaGui.Ira method*), 62

`getLogLevels()` (*iradinapy.iradinaGui.ArgumentParserNoExit method*), 61

`getLogLevelsStr()` (*iradinapy.iradinaGui.ArgumentParserNoExit method*), 61

`getLogs()` (*iradinapy.loggingIra.UnittestStream method*), 66

`getLogsAndClear()` (*iradinapy.loggingIra.UnittestStream method*), 66

`getMainCommandHandler()` (*iradinapy.loggingIra.LoggerIra method*), 64

`getMainConfig()` (*in module iradinapy.configIra*), 56

`getMainConfig()` (*iradinapy.configIra.ConfigManager method*), 56

`getMessage()` (*in module iradinapy.loggingIra*), 67

`getMultiLayerMaterial()` (*iradinapy.caseIradina.CellMultiLayerxIra method*), 50

`getMultiLayerMaterial()` (*iradinapy.caseIradina.StructureIra method*), 54

`getMyLogger()` (*in module iradinapy.example.essai_logging_1*), 44

`getMyLogger()` (*in module iradinapy.example.essai_logging_2*), 44

`getName()` (*iradinapy.analysisIra.ExpressionIra method*), 46

`getNameExpanded()` (*iradinapy.analysisIra.DataIra method*), 46

`getNamesExpanded()` (*iradinapy.analysisIra.ListOfFileViewerXyz method*), 48

`getNamesExpanded()` (*iradinapy.analysisIra.MacroManagerIra method*), 48

`getNoLocal()` (*iradinapy.analysisIra.ListOfFileViewerXyz method*), 48

`getNoLocal()` (*iradinapy.analysisIra.MacroManagerIra method*), 48

`getOptions()` (*iradinapy.iradinaGui.Ira method*), 62

`getOtherUsefulDirsForCpack()` (*in module iradinapy.iradinaFilePatterns*), 60

`getPatternKeys()` (*in module iradinapy.iradinaFilePatterns*), 60

`getRandomConcMaterial()` (*in module iradinapy.analysisIra*), 48

`getRealPath()` (*in module filewatcherpy.fileWatcher*), 73

`getRealPath()` (*iradinapy.configIra.ConfigManager method*), 56

`getRealPath()` (*settingspy.settings.Settings method*), 72

`getRealPath_obsolete()` (*in module filewatcherpy.fileWatcher*), 73

`getSecondsToNow()` (*iradinapy.dateTime.DateTime method*), 57

`getSettings()` (*in module iradinapy.iradinaSettings*), 62

`getSettings()` (*in module settingspy.settings*), 72

`getStdReplaces()` (*in module iradinapy.iradinaFilePatterns*), 60

`getStrDirLogger()` (*in module iradinapy.loggingIra*), 67

`getStrHandler()` (*in module iradinapy.loggingIra*), 67

`getStrLogRecord()` (*in module iradinapy.loggingIra*), 67

`getStrShort()` (*in module iradinapy.loggingIra*), 67

`getT1()` (*iradinapy.dateTime.DeltaTime method*), 58

`getT2()` (*iradinapy.dateTime.DeltaTime method*), 58

`getTargetDirectory()` (*iradinapy.analysisIra.ListOfFileViewerXyz method*), 48

`getTargetDirectory()` (*iradinapy.analysisIra.ListOfUserFileIra method*), 48

`getTypesOfVisualize()` (*in module iradinapy.iradinaFilePatterns*), 60

`getUnittestLogger()` (*in module iradinapy.loggingIra*), 67

`getUsefulDirsForCpack()` (*in module iradinapy.iradinaFilePatterns*), 60

`getUselessDirsForCpack()` (*in module iradinapy.iradinaFilePatterns*), 60

`getUselessFilesForCpack()` (*in module iradinapy.iradinaFilePatterns*), 60

`getUserConfig()` (*iradinapy.analysisIra.MacroManagerIra method*), 48

`napy.configIra.ConfigManager` *method*), 56

`getUserConfigValue()` (*iradina.napy.caseIradina.DensityTargetComponentIra* *method*), 51

`getValue()` (*iradinapy.dateTime.DateTime* *method*), 57

`getValue()` (*iradinapy.dateTime.DeltaTime* *method*), 58

`getVar()` (*in module iradinapy.iradinaSettings*), 62

`getVar()` (*in module settingspy.settings*), 73

`getVar()` (*settingspy.settings.Settings* *method*), 72

`getVersion()` (*in module iradinapy.iradinaGui*), 62

`getVersion()` (*iradina.napy.analysisIra.DataInformationsIra* *method*), 46

`getVisualizeMethod()` (*in module iradina.napy.iradinaFilePatterns*), 60

`getWeekDayNow()` (*in module iradinapy.dateTime*), 59

`getWikipediaValue()` (*iradina.napy.caseIradina.DensityTargetComponentIra* *method*), 51

`getWorkdir()` (*iradinapy.configIra.ConfigManager* *method*), 56

`gitCommit()` (*iradinapy.analysisIra.AnalysisIra* *method*), 45

`gitkLaunch()` (*iradinapy.analysisIra.AnalysisIra* *method*), 45

GREEN (*iradinapy.colorama.ansi.AnsiBack* *attribute*), 40

GREEN (*iradinapy.colorama.ansi.AnsiFore* *attribute*), 41

GREEN (*iradinapy.colorama.winterm.WinColor* *attribute*), 43

`green()` (*in module iradinapy.utilsIra*), 69

GREY (*iradinapy.colorama.winterm.WinColor* *attribute*), 43

H

`header()` (*in module iradinapy.utilsIra*), 69

`HistoryFileManagerXyz` (*class in iradina.napy.analysisIra*), 47

I

`indent()` (*in module iradinapy.coloringIra*), 55

`indent()` (*in module iradinapy.loggingIra*), 67

`indentUnittest()` (*in module iradina.napy.loggingIra*), 67

`info()` (*in module iradinapy.utilsIra*), 70

`init()` (*in module iradinapy.colorama.initialise*), 42

`initLinkForCommand()` (*iradina.napy.loggingIra.LoggerIra* *method*), 64

`initLoggerAsDefault()` (*in module iradina.napy.loggingIra*), 67

`initLoggerAsUnittest()` (*in module iradina.napy.loggingIra*), 67

`initMyLogger()` (*in module iradina.napy.example.essai_logging_1*), 44

`initMyLogger()` (*in module iradina.napy.example.essai_logging_2*), 44

`IonAngleIra` (*class in iradinapy.caseIradina*), 51

`IonBeamIra` (*class in iradinapy.caseIradina*), 51

`IonDistributionIra` (*class in iradina.napy.caseIradina*), 51

`IonDoseIra` (*class in iradinapy.caseIradina*), 52

`IonE0Ira` (*class in iradinapy.caseIradina*), 52

`IonMIra` (*class in iradinapy.caseIradina*), 52

`IonVxIra` (*class in iradinapy.caseIradina*), 52

`IonVyIra` (*class in iradinapy.caseIradina*), 52

`IonVzIra` (*class in iradinapy.caseIradina*), 52

`Ira` (*class in iradinapy.iradinaGui*), 61

`iradinapy` *module*, 70

`iradinapy.abcdExpression` *module*, 45

`iradinapy.analysisIra` *module*, 45

`iradinapy.caseIradina` *module*, 49

`iradinapy.colorama` *module*, 43

`iradinapy.colorama.ansi` *module*, 40

`iradinapy.colorama.ansitowin32` *module*, 41

`iradinapy.colorama.initialise` *module*, 42

`iradinapy.colorama.win32` *module*, 42

`iradinapy.colorama.winterm` *module*, 43

`iradinapy.coloringIra` *module*, 55

`iradinapy.configIra` *module*, 56

`iradinapy.controllerIra` *module*, 57

`iradinapy.controlSimulationIra` *module*, 56

`iradinapy.dateTime` *module*, 57

`iradinapy.example` *module*, 45

`iradinapy.example.essai_logging_1` *module*, 43

`iradinapy.example.essai_logging_2` *module*, 44

`iradinapy.iradinaFilePatterns` *module*, 59

`iradinapy.iradinaGui` *module*, 60

`iradinapy.iradinaSettings` *module*, 62

`iradinapy.loggingIra`

[module](#), 63
[iradinapy.mainWindowIra](#)
 [module](#), 68
[iradinapy.modelIra](#)
 [module](#), 68
[iradinapy.testPrerequisitesIra](#)
 [module](#), 68
[iradinapy.treeViewIra](#)
 [module](#), 68
[iradinapy.utilsIra](#)
 [module](#), 69
[IradinaSettings](#) (class in [iradinapy.iradinaSettings](#)), 62
[is_a_tty\(\)](#) (in module [iradinapy.colorama.ansitowin32](#)), 42
[is_stream_closed\(\)](#) (in module [iradinapy.colorama.ansitowin32](#)), 42
[isEmpty\(\)](#) (in module [iradinapy.configParserUtils.UtSafeConfigParser](#) method), 71
[isHidden\(\)](#) (in module [iradinapy.configIra](#)), 56
[isHidden\(\)](#) ([iradinapy.analysisIra.AnalysisIra](#) method), 45
[isHidden\(\)](#) ([iradinapy.analysisIra.DataInformationsIra](#) method), 46
[isHidden\(\)](#) ([iradinapy.analysisIra.HistoryFileManagerXyz](#) method), 47
[isHidden\(\)](#) ([iradinapy.caseIradina.CaseIra](#) method), 49
[isHidden\(\)](#) ([iradinapy.caseIradina.IonBeamIra](#) method), 51
[isHidden\(\)](#) ([iradinapy.caseIradina.IsotopeIra](#) method), 52
[isHidden\(\)](#) ([iradinapy.caseIradina.MaterialIra](#) method), 53
[isHidden\(\)](#) ([iradinapy.caseIradina.SimulationIra](#) method), 53
[isHidden\(\)](#) ([iradinapy.caseIradina.StructureIra](#) method), 54
[isHidden\(\)](#) ([iradinapy.caseIradina.TargetComponentIra](#) method), 54
[isHidden\(\)](#) ([iradinapy.caseIradina.TargetIra](#) method), 54
[isHidden\(\)](#) ([iradinapy.modelIra.ModelIra](#) method), 68
[isLastRecordHaveNoReturn\(\)](#) ([iradinapy.loggingIra.StreamHandlerIra](#) method), 65
[isNameUnique\(\)](#) ([iradinapy.analysisIra.ExpressionIra](#) method), 46
[isNeedFirstReturn\(\)](#) ([iradinapy.loggingIra.StreamHandlerIra](#) method), 65
[isOk\(\)](#) ([iradinapy.dateTime.DateTime](#) method), 57

[isOk\(\)](#) ([iradinapy.dateTime.DeltaTime](#) method), 58
[IsotopeIra](#) (class in [iradinapy.caseIradina](#)), 52
[isPresentCMakeLists\(\)](#) (in module [iradinapy.iradinaFilePatterns](#)), 60
[isUranieColumn\(\)](#) (in module [iradinapy.iradinaFilePatterns](#)), 60
[isValidExpression\(\)](#) ([iradinapy.analysisIra.ExpressionIra](#) method), 46

J

[join\(\)](#) (in module [iradinapy.analysisIra](#)), 49
[join\(\)](#) (in module [iradinapy.controllerIra](#)), 57

L

[label\(\)](#) (in module [iradinapy.utilsIra](#)), 70
[launchFromSalomePyConsole\(\)](#) (in module [iradinapy.controllerIra](#)), 57
[launchIra\(\)](#) (in module [iradinapy.iradinaGui](#)), 62
[LibraryIra](#) (class in [iradinapy.analysisIra](#)), 47
[LIGHTBLACK_EX](#) ([iradinapy.colorama.ansi.AnsiBack](#) attribute), 40
[LIGHTBLACK_EX](#) ([iradinapy.colorama.ansi.AnsiFore](#) attribute), 41
[LIGHTBLUE_EX](#) ([iradinapy.colorama.ansi.AnsiBack](#) attribute), 40
[LIGHTBLUE_EX](#) ([iradinapy.colorama.ansi.AnsiFore](#) attribute), 41
[LIGHTCYAN_EX](#) ([iradinapy.colorama.ansi.AnsiBack](#) attribute), 40
[LIGHTCYAN_EX](#) ([iradinapy.colorama.ansi.AnsiFore](#) attribute), 41
[LIGHTGREEN_EX](#) ([iradinapy.colorama.ansi.AnsiBack](#) attribute), 40
[LIGHTGREEN_EX](#) ([iradinapy.colorama.ansi.AnsiFore](#) attribute), 41
[LIGHTMAGENTA_EX](#) ([iradinapy.colorama.ansi.AnsiBack](#) attribute), 40
[LIGHTMAGENTA_EX](#) ([iradinapy.colorama.ansi.AnsiFore](#) attribute), 41
[LIGHTRED_EX](#) ([iradinapy.colorama.ansi.AnsiBack](#) attribute), 40
[LIGHTRED_EX](#) ([iradinapy.colorama.ansi.AnsiFore](#) attribute), 41
[LIGHTWHITE_EX](#) ([iradinapy.colorama.ansi.AnsiBack](#) attribute), 40
[LIGHTWHITE_EX](#) ([iradinapy.colorama.ansi.AnsiFore](#) attribute), 41
[LIGHTYELLOW_EX](#) ([iradinapy.colorama.ansi.AnsiBack](#) attribute), 40
[LIGHTYELLOW_EX](#) ([iradinapy.colorama.ansi.AnsiFore](#) attribute), 41
[ListOfAttributeIra](#) (class in [iradinapy.analysisIra](#)), 47

ListOfExpressionIra (class in iradina.py.analysisIra), 47
 ListOfFileViewerXyz (class in iradina.py.analysisIra), 47
 ListOfFunctionIra (class in iradina.py.analysisIra), 48
 ListOfLibraryIra (class in iradina.py.analysisIra), 48
 ListOfMacroIra (class in iradina.py.analysisIra), 48
 ListOfMaterialIra (class in iradina.py.caseIradina), 52
 ListOfTargetComponentsIra (class in iradina.py.caseIradina), 52
 ListOfUserFileIra (class in iradina.py.analysisIra), 48
 listOnlyDirs() (in module iradina.py.iradinaFilePatterns), 60
 localTime() (iradina.py.dateTime.DateTime method), 57
 log() (in module iradina.py.coloringIra), 55
 log() (in module iradina.py.loggingIra), 67
 LoggerIra (class in iradina.py.loggingIra), 64
 logStep() (iradina.py.loggingIra.LoggerIra method), 64
 logStep_begin() (iradina.py.loggingIra.LoggerIra method), 64
 logStep_end() (iradina.py.loggingIra.LoggerIra method), 64

M

MacroIra (class in iradina.py.analysisIra), 48
 MacroManagerIra (class in iradina.py.analysisIra), 48
 MAGENTA (iradina.py.colorama.ansi.AnsiBack attribute), 40
 MAGENTA (iradina.py.colorama.ansi.AnsiFore attribute), 41
 MAGENTA (iradina.py.colorama.winterm.WinColor attribute), 43
 magenta() (in module iradina.py.utilsIra), 70
 MaterialIra (class in iradina.py.caseIradina), 52
 MaterialNameIra (class in iradina.py.caseIradina), 53
 MaxNoIonIra (class in iradina.py.caseIradina), 53
 merge_dicts() (in module iradina.py.utilsIra), 70
 MinEnergyIra (class in iradina.py.caseIradina), 53
 ModelIra (class in iradina.py.modelIra), 68
 module
 configparserpy, 72
 configparserpy.configParserUtils, 71
 configparserpy.test, 71
 configparserpy.test.test_130_configParserUtils, 70
 filewatcherpy, 74
 filewatcherpy.fileWatcher, 73
 filewatcherpy.test, 73

filewatcherpy.test.test_340_fileWatcher, 73
 iradina.py, 70
 iradina.py.abcdExpression, 45
 iradina.py.analysisIra, 45
 iradina.py.caseIradina, 49
 iradina.py.colorama, 43
 iradina.py.colorama.ansi, 40
 iradina.py.colorama.ansitowin32, 41
 iradina.py.colorama.initialise, 42
 iradina.py.colorama.win32, 42
 iradina.py.colorama.winterm, 43
 iradina.py.coloringIra, 55
 iradina.py.configIra, 56
 iradina.py.controllerIra, 57
 iradina.py.controlSimulationIra, 56
 iradina.py.dateTime, 57
 iradina.py.example, 45
 iradina.py.example.essai_logging_1, 43
 iradina.py.example.essai_logging_2, 44
 iradina.py.iradinaFilePatterns, 59
 iradina.py.iradinaGui, 60
 iradina.py.iradinaSettings, 62
 iradina.py.loggingIra, 63
 iradina.py.mainWindowIra, 68
 iradina.py.modelIra, 68
 iradina.py.testPrerequisitesIra, 68
 iradina.py.treeViewIra, 68
 iradina.py.utilsIra, 69
 settingspy, 73
 settingspy.setStyleFactory, 72
 settingspy.settings, 72

MSG_UNDEFINED (iradina.py.dateTime.DateTime attribute), 57
 MSG_UNDEFINED (iradina.py.dateTime.DeltaTime attribute), 58
 MyFormatter (class in iradina.py.example.essai_logging_2), 44

N

NORMAL (iradina.py.colorama.ansi.AnsiStyle attribute), 41
 NORMAL (iradina.py.colorama.winterm.WinStyle attribute), 43
 normal() (in module iradina.py.utilsIra), 70
 normalize() (in module iradina.py.analysisIra), 49
 normalize() (iradina.py.caseIradina.DensityIra method), 50
 normalize() (iradina.py.caseIradina.MaterialIra method), 53
 NormalizeOutputIra (class in iradina.py.caseIradina), 53

O

on_attributesChange() (iradina.py.caseIradina.IsotopeIra method),

52
on_attributesChange() (iradina-
 napy.caseIradina.TargetComponentIra
 method), 54

P

packageLaunch() (iradi-
 napy.analysisIra.AnalysisIra *method*),
 45
parse_date() (in module *iradinapy.dateTime*), 59
parseArguments() (iradinapy.iradinaGui.Ira
 method), 62
Popen() (in module *iradinapy.utilsIra*), 69
POS() (iradinapy.colorama.ansi.AnsiCursor *method*),
 40
postTreatments() (iradi-
 napy.analysisIra.AnalysisIra *method*),
 45
print_help() (iradinapy.iradinaGui.Ira *method*),
 62
printROOTContext() (iradi-
 napy.analysisIra.AnalysisIra *method*),
 45

R

raiseIfKo() (iradinapy.dateTime.DateTime
 method), 57
raiseIfKo() (iradinapy.dateTime.DeltaTime
 method), 58
readDefaultAndUser() (config-
 parserpy.configParserUtils.UtSafeConfigParser
 method), 71
readFromStr() (config-
 parserpy.configParserUtils.UtSafeConfigParser
 method), 71
RED (iradinapy.colorama.ansi.AnsiBack attribute), 40
RED (iradinapy.colorama.ansi.AnsiFore attribute), 41
RED (iradinapy.colorama.winterm.WinColor attribute),
 43
red() (in module *iradinapy.utilsIra*), 70
reinit() (in module *iradinapy.colorama.initialise*),
 42
remove_item_from_list() (in module *iradi-*
 napy.utilsIra), 70
removeDuplicates() (in module *iradi-*
 napy.iradinaFilePatterns), 60
replace() (in module *iradinapy.coloringIra*), 55
replace_in_file() (in module *iradi-*
 napy.utilsIra), 70
RESET (iradinapy.colorama.ansi.AnsiBack attribute),
 40
RESET (iradinapy.colorama.ansi.AnsiFore attribute),
 41
reset() (in module *iradinapy.utilsIra*), 70
RESET_ALL (iradinapy.colorama.ansi.AnsiStyle at-
 tribute), 41
reset_all() (in module *iradi-*
 napy.colorama.initialise), 42

reset_all() (iradi-
 napy.colorama.ansitowin32.AnsiToWin32
 method), 42
reset_all() (iradi-
 napy.colorama.winterm.WinTerm *method*),
 43
run() (in module *settingspy.setStyleFactory*), 72
runGUI() (iradinapy.iradinaGui.Ira *method*), 62
runPythonCode() (iradi-
 napy.analysisIra.AnalysisIra *method*),
 45

S

searchURANIEMethod() (iradi-
 napy.analysisIra.AnalysisIra *method*),
 45
Seed1Ira (class in *iradinapy.caseIradina*), 53
Seed2Ira (class in *iradinapy.caseIradina*), 53
SeedIra (class in *iradinapy.caseIradina*), 53
set_attrs() (iradi-
 napy.colorama.winterm.WinTerm *method*),
 43
set_config() (iradinapy.loggingIra.XmlHandler
 method), 66
set_console() (iradi-
 napy.colorama.winterm.WinTerm *method*),
 43
set_cursor_position() (iradi-
 napy.colorama.winterm.WinTerm *method*),
 43
set_target_file() (iradi-
 napy.loggingIra.XmlHandler *method*),
 66
set_title() (in module *iradinapy.colorama.ansi*),
 41
set_title() (iradi-
 napy.colorama.winterm.WinTerm *method*),
 43
setAttributes() (iradinapy.analysisIra.DataIra
 method), 46
setCalculatedValue() (iradi-
 napy.caseIradina.DensityIra *method*),
 50
setColorLevelname() (iradi-
 napy.loggingIra.DefaultFormatter *method*),
 63
setConfirmMode() (iradinapy.iradinaGui.Ira
 method), 62
SetConsoleTextAttribute() (in module *iradi-*
 napy.colorama.win32), 42
setCurrentMode() (in module *iradi-*
 napy.configIra), 56
setDefaultDensityUser() (iradi-
 napy.caseIradina.DensityTargetComponentIra
 method), 51
setDefaultDensityWiki() (iradi-
 napy.caseIradina.DensityTargetComponentIra
 method), 51

`setDefaultValues()` (*iradina.napy.analysisIra.AnalysisIra* method), 45
`setDefaultValues()` (*iradina.napy.analysisIra.DataInformationsIra* method), 46
`setDefaultValues()` (*iradina.napy.analysisIra.HistoryFileManagerXyz* method), 47
`setDefaultValues()` (*iradina.napy.analysisIra.MacroManagerIra* method), 48
`setDefaultValues()` (*iradina.napy.caseIradina.CaseIra* method), 49
`setDefaultValues()` (*iradina.napy.caseIradina.IsotopeIra* method), 52
`setDefaultValues()` (*iradina.napy.caseIradina.TargetComponentIra* method), 54
`setDefaultValues()` (*iradina.napy.controlSimulationIra.ControlSimulationIra* method), 56
`setDefaultValues()` (*iradina.napy.modelIra.ModelIra* method), 68
`setEnvVar()` (in module *iradina.napy.iradinaSettings*), 63
`setEnvVar()` (in module *settingspy.settings*), 73
`setEnvVarByDefault()` (in module *iradina.napy.iradinaSettings*), 63
`setEnvVarByDefault()` (in module *settingspy.settings*), 73
`setFileHandlerForCommand()` (*iradina.napy.loggingIra.LoggerIra* method), 65
`setFromFileIra()` (*iradina.napy.modelIra.ModelIra* method), 68
`setLevelMainHandler()` (*iradina.napy.loggingIra.LoggerIra* method), 65
`setMainConfig()` (*iradina.napy.configIra.ConfigManager* method), 56
`setT1()` (*iradina.napy.dateTime.DeltaTime* method), 58
`setT2()` (*iradina.napy.dateTime.DeltaTime* method), 58
`Settings` (class in *settingspy.settings*), 72
`settingspy` module, 73
`settingspy.setStyleFactory` module, 72
`settingspy.settings` module, 72
`setValue()` (*iradina.napy.dateTime.DateTime* method), 58
`setVar()` (*settingspy.settings.Settings* method), 72
`should_wrap()` (*iradina.napy.colorama.ansitowin32.AnsiToWin32* method), 42
`show_doc()` (*iradina.napy.iradinaGui.Ira* method), 62
`SimulationIra` (class in *iradina.napy.caseIradina*), 53
`SimulationTypeIra` (class in *iradina.napy.caseIradina*), 53
`sleep()` (in module *iradina.napy.dateTime*), 59
`sleep()` (in module *iradina.napy.utilsIra*), 70
`StatusUpdateIntervalIra` (class in *iradina.napy.caseIradina*), 54
`step()` (*iradina.napy.loggingIra.LoggerIra* method), 65
`StorageIntervalIra` (class in *iradina.napy.caseIradina*), 54
`StorePathLimitIra` (class in *iradina.napy.caseIradina*), 54
`StorePathLimitRecoilsIra` (class in *iradina.napy.caseIradina*), 54
`StragglngModelIra` (class in *iradina.napy.caseIradina*), 54
`strCfg()` (*iradina.napy.caseIradina.BoolFalseIra* method), 49
`strCfg()` (*iradina.napy.caseIradina.CompositionFileTypeIra* method), 50
`strCfg()` (*iradina.napy.caseIradina.DensityIra* method), 50
`strCfg()` (*iradina.napy.caseIradina.FlightLengthTypeIra* method), 51
`strCfg()` (*iradina.napy.caseIradina.IonDistributionIra* method), 52
`strCfg()` (*iradina.napy.caseIradina.NormalizeOutputIra* method), 53
`strCfg()` (*iradina.napy.caseIradina.SimulationTypeIra* method), 54
`strCfg()` (*iradina.napy.caseIradina.StragglngModelIra* method), 54
`strCfg()` (*iradina.napy.caseIradina.TypeCompositionIra* method), 55
`StreamHandlerIra` (class in *iradina.napy.loggingIra*), 65
`StreamWrapper` (class in *iradina.napy.colorama.ansitowin32*), 42
`StructureIra` (class in *iradina.napy.caseIradina*), 54
`style()` (*iradina.napy.colorama.winterm.WinTerm* method), 43
`success()` (in module *iradina.napy.utilsIra*), 70

T

`tabColor()` (in module *iradina.napy.utilsIra*), 70
`TargetComponentIra` (class in *iradina.napy.caseIradina*), 54
`TargetIra` (class in *iradina.napy.caseIradina*), 54
`test_000()` (*configparser.py.test.test_130_configParserUtils.TestCase* method), 71
`test_010()` (*configparser.py.test.test_130_configParserUtils.TestCase* method), 71
`test_010()` (*filewatcher.py.test.test_340_fileWatcher.TestCase* method), 73
`test_020()` (*configparser.py.test.test_130_configParserUtils.TestCase* method), 71

test_020() (filewatcherpy.test.test_340_fileWatcher.TestCase napy.abcdExpression), 45
method), 73 toEval0123() (iradi-

test_030() (config- napy.caseIradina.CellMultiLayerxIra
parserpy.test.test_130_configParserUtils.TestCase method), 50
method), 71 toEvalAbcd() (in module iradi-

test_030() (filewatcherpy.test.test_340_fileWatcher.TestCase napy.abcdExpression), 45
method), 73 toEvalAbcd() (iradi-

test_032() (config- napy.caseIradina.CellMultiLayerxIra
parserpy.test.test_130_configParserUtils.TestCase method), 50
method), 71 toEvalAbcdForTooltip() (in module iradi-

test_034() (config- napy.abcdExpression), 45
parserpy.test.test_130_configParserUtils.TestCase toFileCompositionIn() (in module iradi-
method), 71 napy.analysisIra), 49

test_100() (config- toFileConfigurationIn() (in module iradi-
parserpy.test.test_130_configParserUtils.TestCase napy.analysisIra), 49
method), 71 toFileIra() (iradinapy.analysisIra.AnalysisIra

test_999() (config- method), 45
parserpy.test.test_130_configParserUtils.TestCase toFileMaterialIn() (in module iradi-
method), 71 napy.analysisIra), 49

test_999() (filewatcherpy.test.test_340_fileWatcher.TestCase toCaseStructureIn() (in module iradi-
method), 73 napy.analysisIra), 49

TestCase (class in config- toMinutes() (iradinapy.dateTime.DeltaTime
parserpy.test.test_130_configParserUtils), method), 59
71 toOrderedDict() (config-

TestCase (class in file- parserpy.configParserUtils.UtSafeConfigParser
watcherpy.test.test_340_fileWatcher), 73 method), 72

TestImports() (in module iradi- toSeconds() (iradinapy.dateTime.DateTime
napy.testPrerequisitesIra), 68 method), 58

TestIradinaFeatures() (in module iradi- toSeconds() (iradinapy.dateTime.DeltaTime
napy.testPrerequisitesIra), 68 method), 59

testLogger1() (in module iradi- toStrDateConfig() (iradi-
napy.example.essai_logging_1), 44 napy.dateTime.DateTime method), 58

testLogger1() (in module iradi- toStrDateHourConfig() (iradi-
napy.example.essai_logging_2), 44 napy.dateTime.DateTime method), 58

testLogger_1() (in module iradinapy.loggingIra), toStrFile() (iradinapy.dateTime.DateTime
67 method), 58

testMain() (in module iradinapy.loggingIra), 67 toStrHms() (iradinapy.dateTime.DeltaTime
testNoReturn() (in module iradinapy.loggingIra), method), 59
67 toStrHourConfig() (iradi-

testNoReturn() (iradinapy.loggingIra.LoggerIra napy.dateTime.DateTime method), 58
method), 65 toStrHuman() (iradinapy.dateTime.DateTime
method), 58

timedelta_total_seconds() (in module iradi- toStrHuman() (iradinapy.dateTime.DeltaTime
napy.dateTime), 59 method), 59

toAbcd() (in module iradinapy.abcdExpression), 45 toStrIra() (iradinapy.modelIra.ModelIra method),
toAtomCm3() (iradinapy.caseIradina.DensityIra 68
method), 51 toStrPackage() (iradinapy.dateTime.DateTime
method), 58

toCatchAll() (config- toStrXml() (iradinapy.dateTime.DateTime method),
parserpy.configParserUtils.UtSafeConfigParser 58
method), 71 toValue() (in module iradinapy.analysisIra), 49

toColor() (in module iradinapy.coloringIra), 55 toVx() (iradinapy.caseIradina.IonAngleIra method),
toColor_AnsiToWin32() (in module iradi- toVy() (iradinapy.caseIradina.IonAngleIra method),
napy.coloringIra), 55 51

toDict() (configparserpy.configParserUtils.UtSafeConfigParser toXml() (iradinapy.caseIradina.CellDepthxIra
method), 71 method), 50

toDictTuple() (config- toXml() (iradinapy.caseIradina.DensityIra method),
parserpy.configParserUtils.UtSafeConfigParser 50
method), 72

toEval0123() (in module iradi- toXml() (iradinapy.caseIradina.DensityIra method),

51
 toXml() (*iradinapy.caseIradina.IonAngleIra*
method), 51
 trace() (*iradinapy.loggingIra.LoggerIra* *method*),
 65
 TypeCompositionIra (*class in iradi-*
napy.caseIradina), 55

U

UnittestFormatter (*class in iradi-*
napy.loggingIra), 65
 UnittestStream (*class in iradinapy.loggingIra*),
 66
 UP() (*iradinapy.colorama.ansi.AnsiCursor* *method*),
 40
 updateRootlogonLaunch() (*iradi-*
napy.analysisIra.AnalysisIra *method*),
 45
 userExpand() (*iradinapy.modelIra.ModelIra*
method), 68
 UserFileIra (*class in iradinapy.analysisIra*), 48
 userMode() (*iradinapy.modelIra.ModelIra* *method*),
 68
 UserModeIra (*class in iradi-*
napy.controlSimulationIra), 56
 UtSafeConfigParser (*class in config-*
parserpy.configParserUtils), 71

V

verboseEvent (*in module iradinapy.treeViewIra*),
 68
 visualize_TDS_graphic() (*in module iradi-*
napy.iradinaFilePatterns), 60
 visualize_TDS_univariate() (*in module*
iradinapy.iradinaFilePatterns), 60

W

warning() (*in module iradinapy.utilsIra*), 70
 WHITE (*iradinapy.colorama.ansi.AnsiBack* *attribute*),
 40
 WHITE (*iradinapy.colorama.ansi.AnsiFore* *attribute*),
 41
 white() (*in module iradinapy.utilsIra*), 70
 winapi_test() (*in module iradi-*
napy.colorama.win32), 42
 WinColor (*class in iradinapy.colorama.winterm*), 43
 WinStyle (*class in iradinapy.colorama.winterm*), 43
 WinTerm (*class in iradinapy.colorama.winterm*), 43
 wrap_stream() (*in module iradi-*
napy.colorama.initialise), 42
 write() (*iradinapy.colorama.ansitowin32.AnsiToWin32*
method), 42
 write() (*iradinapy.colorama.ansitowin32.StreamWrapper*
method), 42
 write() (*iradinapy.coloringIra.ColoringStream*
method), 55
 write() (*iradinapy.loggingIra.UnittestStream*
method), 66

write_and_convert() (*iradi-*
napy.colorama.ansitowin32.AnsiToWin32
method), 42
 write_plain_text() (*iradi-*
napy.colorama.ansitowin32.AnsiToWin32
method), 42
 writeToStr() (*config-*
parserpy.configParserUtils.UtSafeConfigParser
method), 72

X

XmlHandler (*class in iradinapy.loggingIra*), 66
 xx_isEnabledFor() (*iradi-*
napy.loggingIra.LoggerIra *method*), 65

Y

YELLOW (*iradinapy.colorama.ansi.AnsiBack* *attribute*),
 40
 YELLOW (*iradinapy.colorama.ansi.AnsiFore* *attribute*),
 41
 YELLOW (*iradinapy.colorama.winterm.WinColor* *at-*
tribute), 43
 yellow() (*in module iradinapy.utilsIra*), 70